

Import/Export Guide

July 8, 2025

For the most recent version of this document, visit our **documentation website**.

Table of Contents

1 Import/Export overview	6
1.1 Getting started with Import/Export checklist	6
1.2 Available import and export workflows	7
1.3 Import/Export transfer modes	8
1.4 Considerations when to use and not use Express Transfer with Import/Export	8
1.5 Supported file types	9
1.6 Data upload size limitation	9
1.7 Concurrent and consecutive jobs	10
2 Installing Import/Export	11
2.1 Requirements	11
2.1.1 Workspace requirements	11
2.1.2 Port Access	11
2.2 Installing Import/Export	11
3 Permissions	13
4 Import/Export load file specifications	15
4.1 Supported file types	15
4.2 Metadata, extracted text, and native files	15
4.2.1 Encoding	16
4.2.2 Header row	17
4.2.3 Fields	17
4.2.4 Accepted date formats	19
4.2.5 Delimiters	21
4.2.6 Default delimiters	22
4.2.7 ZIP archive with extracted text and natives	22
4.3 Image and extracted text files	23
4.3.1 Supported image file formats	23
4.3.2 Load file format	23
4.3.3 ZIP archive with images	24
4.3.4 Importing extracted text during an image load	24
4.4 Processed data	24


4.5 Transcript file types supported	25
4.6 Access DB (MDB) load file specifications	25
4.6.1 Export table	25
4.6.2 Parties Table	26
4.6.3 Pages table	27
4.6.4 Export_Extras table	27
4.6.5 Example of values in Export_Extras table	28
4.6.6 Export recommendations	28
5 General recommendations for structured data import and export jobs	29
5.1 Load file import recommendations	29
5.2 Load file export recommendations	29
6 Express Transfer overview	31
6.1 Prerequisites	31
6.2 Considerations when to use and not use Express Transfer with Import/Export	31
6.3 Express Transfer overview	32
6.3.1 Prerequisites	32
6.3.2 Considerations when to use and not use Express Transfer with Import/Export	33
6.4 Installing and updating Express Transfer desktop application	33
6.4.1 Requirements	33
6.4.2 Prerequisites	34
6.4.3 Installing Express Transfer	34
6.4.4 Silent installation of Express Transfer	37
6.4.5 Locating the Express Transfer version number	38
6.4.6 Automatically checking for software updates	40
6.4.7 Manually checking for software updates	43
6.5 Activating and deactivating Express Transfer	44
6.5.1 Prerequisites	44
6.5.2 Considerations when to use and not use Express Transfer with Import/Export	44
6.5.3 Activating Express Transfer	45
6.5.4 Deactivating Express Transfer	47
6.5.5 Data transfer performance considerations	47
6.6 Express Transfer system tray menu	49

	6.7 Express Transfer Preferences	50
	6.7.1 Automatically checking for software updates	50
	6.7.2 Limit bandwidth	53
	6.7.3 Exclude temporary Microsoft Office files from data import	57
	6.7.4 Configuring proxy settings	60
	6.8 Express Transfer Connectivity check	63
	6.8.1 Network Throughput Check	66
	6.9 Express Transfer Job tracking and history	66
	6.10 Express Transfer reporting jobs failed or completed with errors	71
7	Importing data using Import/Export	74
	7.1 Pre-check Load File	74
	7.1.1 Document and RDO load file import	74
	7.1.2 Image and Production load file import	76
	7.1.3 Working with Pre-check Load File results	77
	7.2 Importing data using Import/Export	77
	7.2.1 Pre-check Load File	78
	7.3 Importing a document load file	80
	7.4 Importing an image load file	93
	7.5 Importing a production load file	102
	7.6 Importing an RDO load file	111
	7.7 Importing an Access DB load file (MDB)	123
	7.8 Importing transcript MDB data for Processing via Import/Export Limited General Availability .	131
	7.8.1 Before you begin	131
	7.8.2 Importing transcript MDB data	132
	7.9 Importing raw unprocessed data for Processing via Import/Export	138
8	Exporting data using Import/Export	147
	8.1 Exporting data using Import/Export	147
	8.2 Exporting a folder load file	147
	8.3 Exporting a production set load file	162
	8.4 Exporting an RDO load file	176
	8.5 Exporting a saved search load file	189
	8.6 Exporting a saved search or a folder with Access DB load file (MDB)	204

8.7 Exporting a production set with Access DB load file (MDB)	217
9 Import/Export Job tracking and history	228
9.1 Reviewing the Import/Export Job page	228
9.2 Support for Mass Operations	229
10 Import/Export queue	230

1 Import/Export overview

Import/Export provides an efficient and streamlined ability to import raw data files, document load files, image load files, production files, RDO files, as well as to export folders and subfolders, production sets, saved searches, and RDO files. It is the recommended method for importing and exporting data for RelativityOne.



You can use Import/Export with or without activating Express Transfer, however, we recommend activating Express Transfer. For more information on Express Transfer, see Express Transfer on page 32 and review the section below on considerations when to use and not use Express Transfer.

Notes:

- For customers whose file shares haven't been fully migrated to ADLS yet, Import/Export offers a solution where the import process utilizes the primary file share to store the uploaded data. See the Community article Import/Export uses ADLS if one is present on the tenant for details.
- After documents are imported using Import/Export, you can automate creating a dtSearch index or run a search terms report with those documents using Automated Workflows

1.1 Getting started with Import/Export checklist

Ready to get up-to-speed with Import/Export? Learn more about the functionality, how to get it installed in your instance of RelativityOne, and workflow specifics with the resources listed below.

Overview Sessions:

Take a deeper dive by watching our recorded <u>Import/Export Foundations: Comprehensive Overview</u> webinar, in addition to other Import/Export self-paced webinars on the <u>Relativity Learning site under Data Ingestion & Management</u>.

Before you can start working with Import/Export, you will have to set things up in your RelativityOne instance:

- 1. Reach out to your IT Department and ensure <u>TCP port 443</u> is open to transfer data in RelativityOne with Express Transfer.
- 2. Install Import/Export from the Relativity Application Library.
- Open Import/Export and <u>install Express Transfer</u> for larger data transfers and to streamline structured data loads. Only complete this step if your organization intends to use Express Transfer with Import/Export.
- 4. Ensure that users have the proper permissions.

Note: As of February 2025, the new Feature Permissions redefines Relativity's security management by shifting the focus from Object Types and Tab Visibility to feature-based permissions. This new method is simply another option; any feature-specific permissions information already in this topic is still applicable. This new interface enables administrators to manage permissions at the feature level, offering a more intuitive experience. By viewing granular permissions associated with each feature, administrators can ensure comprehensive control, ultimately reducing complexity and minimizing errors. For details see Instance-level permissions and Workspace-level permissions.

Now that Import/Export is set up, you are ready to perform these workflows and benchmark your speeds:

- Import data, both structured and unstructured
- Export folders, RDO data, productions and saved searches
- Import and export data using Express Transfer with Import/Export
- View the Job History

Have questions?

- Submit a ticket to Customer Supportfor workflow assistance.
- Visit our What's New page, Relativity Documentation or our Community Site.
- · Contact Relativity Customer Support.

1.2 Available import and export workflows

The following workflows can be performed using Import/Export.

- · Import workflows:
 - Unstructured Data —Unprocessed/unstructured files and transcript MDB data that require processing
 - Raw (Unprocessed) data workflow with Processing
 - · Transcript data for Processing

- Structured (Processed) Data—Structured data includes natives, text, image, and PDF files, and load files containing metadata.
 - · Document load file import
 - · Image load file import
 - · Production load file import
 - · Relativity Dynamic Object load file import
 - Access DB load file import (MDB) (for Asia-Pacific region only)

• Export workflows:

- Folder export
- · Production set export
- · Saved Search export
- RDO export
- Saved Search or Folder with Access DB export (MDB) (for Asia-Pacific region only)
- Production set with Access DB export (MDB) (for Asia-Pacific region only)

1.3 Import/Export transfer modes

There are two methods available to transfer data using Import/Export. Refer to the next section for considerations when to use each one.

• Import/Export with Express Transfer

This refers to activating Express Transfer within Import/Export to transfer data into and out of RelativityOne. This mode is the recommended method for data transfer. Express Transfer is a separately installed desktop application that sits outside of the RelativityOne browser software and handles the data transfer process. See Express Transfer overview and Installing Express Transfer for more information.

Import/Export only

This refers to only using the Import/Export browser application within the RelativityOne software to import and export data without Express Transfer activated. This mode is sometimes referred to as web mode or web only mode. See Installing Import/Export. Even if the Express Transfer application is installed on the desktop, it must not be activated when using web mode.

1.4 Considerations when to use and not use Express Transfer with Import/Export

We recommend using Import/Export with Express Transfer activated whenever possible for all importing and exporting workflows, and particularly when:

- data file size is greater than 20GB, although Express Transfer can be used for any size data transfer.
- processing multiple import jobs. The jobs will be queued and executed when the previous job is complete.
- slow or unstable network connection. Express Transfers enables you to retry the upload.

Use Import/Export without activating Express Transfer when:

- your company policy prohibits installing desktop applications.
- your network configuration does not allow third party applications to send or receive data, such as proxy settings.
- data file size is less than 20GB.
- · data is in ZIP files.

Note: You need to use Express Transfer to upload and process encrypted materials, such as password-protected zip files or Case files (L01/N01) that require Password Bank functionality. If you cannot use Express Transfer for such imports, zip your encrypted materials in a single unencrypted ZIP container. The 20 GB limit for the zip file size applies. Import/Export will transfer and extract the top-level zip file, preparing your encrypted materials for Processing. Then, Processing will utilize Password Bank to decrypt materials.

1.5 Supported file types

Import/Export supports the following file types. Refer to Import/Export load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

- **ZIP and PST files**—for transferring data to the server-side.
- **Native files for processing**—see the list of supported file types for processing within the Processing quide.
- Document Load File import—.dat, .csv and .txt load files.
- Image Load File import—Opticon-formatted page-level files. Formats supported: single page TIFF (Group IV) files, single page JPG files, and single and multiple PDF files.
- Access DB load file import—.mdb or accdb. For more information, see <u>Access DB (MDB) load file</u> specifications.

Note: RelativityOne allows users to restrict given file types from being imported into their instances with the RestrictedFileTypes instance setting. Import/Export reads and applies this instance setting when importing materials into RelativityOne, therefore, all file types listed as restricted file types will be skipped.

1.6 Data upload size limitation

When Express Transfer is activated for use with Import/Export, there is no data upload limit. See Express Transfer overview and Activating Express Transfer for more information.

When Express Transfer is not activated for use with Import/Export, the application accepts single .zip or .pst containers or a single structured import data set load file up to 20GB for a single import.

1.7 Concurrent and consecutive jobs

The concurrent or consecutive nature of a job depends on what stage the job is at, which data transfer mode you're using: web only or Express Transfer, and what type of job you're running: Processing, Import, or Export. For more information, see the Community article Import/Export Concurrent and Consecutive Jobs.

2 Installing Import/Export

The Import/Export application will not be installed automatically in all your workspaces so you must do so manually in each one from the Relativity Application Library.

2.1 Requirements

Refer to the sections below for the necessary requirements for Import/Export.

2.1.1 Workspace requirements

When using Import/Export, you need the following RelativityOne applications installed in your workspace from the Relativity Application Library:

Note: Import/Export requires the *Relativity.Transfer.Service* to be installed in your RelativityOne instance. This is a global RelativityOne application that is installed and updated automatically.

- · Import/Export; see installation steps below
- Export
- Import
- Processing; only required if you intend to process <u>unstructured raw data for processing</u> with Import/Export
- Relativity Lists (version 1.2.305 or newer)

Note: Import/Export requires Relativity Lists version 1.2.305 or newer to be installed and enabled in the workspace for running import and export jobs. If the Relativity Lists application is not available, all Import/Export workflows will be disabled.

2.1.2 Port Access

Import/Export requires TCP port 443 to be open to transfer data. For further assistance, please contact your IT Department. Also refer to the Import Export Application - Required Ports article in Community for additional information.

2.2 Installing Import/Export

To manually install Import/Export in the workspace:

- 1. Log into RelativityOne as an Admin user.
- 2. Navigate to the Application Library.
- 3. Type Import/Export in the Name field's filter and press Enter.
- 4. Click the **Import/Export** application name to go to the **Application Information** tab.
- 5. Click **Select** in the Workspaces Installed pane.

- 6. Find and select your workspace(s) and click the **right arrow** button to move it to the right-hand pane.
- 7. Click Apply.

If you want to use Import/Export with Express Transfer, which is recommended in most cases, you must activate Express Transfer within the Import/Export application. Refer to Express Transfer on page 45 for more information.

3 Permissions

Note: As of February 2025, the new Feature Permissions redefines Relativity's security management by shifting the focus from Object Types and Tab Visibility to feature-based permissions. This new method is simply another option; any feature-specific permissions information already in this topic is still applicable. This new interface enables administrators to manage permissions at the feature level, offering a more intuitive experience. By viewing granular permissions associated with each feature, administrators can ensure comprehensive control, ultimately reducing complexity and minimizing errors. For details see Instance-level permissions and Workspace-level permissions.

Import/Export validates the user's permissions and checks if all required applications are installed in their workspace. If the user does not have permission to run a given workflow or if any application needed for that workflow is not installed, Import/Export grays out the workflow button and displays a warning message below it explaining why it's inactive. This validation process works separately for each workflow. For example, if a user does not have permission to run a Processing job, they may still be able to import load file data but will not be able to process it.

All permissions are set in Workspace security.

The following permissions are required for **all** import and export workflows:

Object security	Tab visibility	Other Set- tings
Document—Add, Edit, View	Documents	
• Folder—Add, Edit	Import/Export	
Import/Export Extraction Job—Add, Edit	Job	
• Import/Export Job—Add, Edit		
Relativity Time Zone—View		

Additional permissions required for Raw (Unprocessed) Data import and Transcript MDB Data import workflows only:

Object security	Tab visibility	Other Settings
• Entity—Add, Edit		Mass operations
OCR Language—View		Allow Import
Processing Data Source—Add, Edit, View		Allow Staging
Processing Error—Add, Edit		Import
Processing Set—Add, Edit, View		
Quick Create Set—Add, Edit		

Additional permissions required for Structured Data import workflows only:

Object security	Tab visibility	Other Settings
• Production—View		Admin operations
Relativity Import Data Source—Add, Edit, View		Allow Import Allow Staging
Relativity Import Job—Add, Edit, View		Import

Note: Import/Export now allows importing data directly from the Staging locations, such as StructuredData (load file) and ProcessingSource (raw data). The Allow Staging Import permission is required to activate these import options in the application UI.

Additional permissions required for **Export workflows** only:

Object security	Tab visibility	Other Settings
Import/Export Job—Add, Edit		Admin operations
• Production—View		• Allow
Relativity Export Service Job—Add, Edit, View		Export

4 Import/Export load file specifications

A load file is used to transfer data and its associated metadata into a database. During import, the application reads the load file to determine what metadata should be written into each field and to copy it to the workspace. If your organization uses a processing vendor, you'll need to upload case data with a load file. You'll also use load files when you receive a subset of data from another party, such as a production from opposing counsel.

Below are the load file specifications for Import/Export.

4.1 Supported file types

Import/Export supports the following file types.

- **ZIP and PST files**—for transferring data to the server-side.
- **Native files for processing**—see the list of supported file types for processing within the Processing guide.
- Document Load File import—.dat, .csv and .txt load files.
- Image Load File import—Opticon-formatted page-level files. Formats supported: single page TIFF (Group IV) files, single page JPG files, and single and multiple PDF files.
- Access DB load file import—.mdb or accdb. For more information, see <u>Access DB (MDB) load file</u> specifications.

Note: RelativityOne allows users to restrict given file types from being imported into their instances with the RestrictedFileTypes instance setting. Import/Export reads and applies this instance setting when importing materials into RelativityOne, therefore, all file types listed as restricted file types will be skipped.

Import/Export web only accepted file types:

For Unstructured Processing Jobs

- PST—Individual Entity and Custodian files
- ZIP containers:
 - · All loose files must be in a ZIP container
 - · Entity and Custodian identifier at the folder level

For Load Files and Structured Data Sets

- Load file—Keep the Load File (.dat, .opt, etc.) separate from zipped documents
- Files—Native or Image/Production files must be in a ZIP container

4.2 Metadata, extracted text, and native files

Import/Export uses a flat, document-level load file to load metadata, document level extracted text, and natives files. Each line should represent one document.

4.2.1 Encoding

You must choose the proper encoding of a file when a load file is first selected. Import/Export supports the following encodings:

- Arabic (ASMO 708)
- Arabic (ISO)
- · Arabic (Windows)
- · Baltic (ISO)
- · Baltic (Windows)
- Central European (ISO)
- · Central European (Windows)
- Chinese Simplified (GB18030)
- Chinese Simplified (GB2312)
- Chinese Traditional (Big5)
- Cyrillic (DOS)
- Cyrillic (ISO)
- Cyrillic (KOI8-R)
- Cyrillic (KOI8-U)
- · Cyrillic (Mac)
- Cyrillic (Windows)
- · Estonian (ISO)
- · Greek (ISO)
- · Greek (Windows)
- · Hebrew (ISO-Logical)
- Hebrew (ISO-Visual)
- Hebrew (Windows)
- Japanese (EUC)
- Japanese (JIS 0208-1990 and 0212-1990)
- Japanese (JIS)
- Japanese (JIS-Allow 1 byte Kana SO/SI)
- Japanese (JIS-Allow 1 byte Kana)
- Japanese (Shift-JIS)

- Korean
- Korean (EUC)
- Latin 3 (ISO)
- Latin 9 (ISO)
- Thai (Windows)
- Turkish (ISO)
- Turkish (Windows)
- Ukrainian (Mac)
- Unicode (UTF-16)
- Unicode (Big-Endian)
- Unicode (UTF-8)
- US-ASCII
- Vietnamese (Windows)
- Western European (ISO)
- Western European (Mac)
- Western European (Windows)

4.2.2 Header row

Import/Export does not require load file header rows. However, they are strongly recommended to ensure accuracy.

The field names in your header do not need to match the field names in your workspace.

4.2.3 Fields

RelativityOne doesn't require any specific load file field order. You can create any number of workspace fields to store metadata or coding.

During the load process, you can match your load file fields to the fields in your workspace. The identifier field is required for each load. When loading new records, this is your workspace identifier.

When performing an overlay, you can use the workspace identifier or select another field as the identifier. This is useful when overlaying production data. For example, you could use the Bates number field rather than the document identifier in the workspace.


All fields except Identifier are optional; however, you may find some of the following system fields beneficial.

- 1. Identifier—the unique identifier of the record.
- 2. **Group Identifier**—the identifier of a document's family group.
 - The group identifier repeats for all records in the group.
 - Usually, this is the document identifier of the group's parent document. For example:
 - If an email with the document identifier of AS00001 has several attachments, the email and its attachments have a group identifier of AS00001.
 - If a group identifier for a record is not set, the document identifier populates the group identifier field in the case. This effectively creates a "group" of one document.
- 3. MD5 Hash—the duplicate hash value of the record.
 - · You can enter any type of hash value, and rename the field in your case.
 - If documents share the same hash value, the software identifies the documents as a duplicate group.
 - If a hash field for a record is not set, the document identifier populates the hash field in the case. This effectively creates a "group" of one document.
- 4. **Extracted Text**—the text of the document. Either the OCR or Full Text. The extracted text appears in the viewer and is added to search indexes. This field can contain either:
 - · The actual OCR or Full Text.
 - The path to a document level text file containing the OCR or Full Text. Both relative and absolute (full) paths are supported; however, to import load file data that contains absolute paths, Express Transfer must be activated. Relative paths can start with Blank or .\, as in: MainFolder\SubFolder\File.extension. Absolute paths can start with a backslash (\), as in: \MainFolder\SubFolder\File.extension.
- 5. **Native File Path**—the path to any native files you would like to load. Both relative and absolute (full) paths are supported; however, to import load file data that contains absolute paths, Express Transfer must be activated. Relative paths can start with Blank or .\, as in: *MainFolder-\SubFolder\File.extension* or .*MainFolder\SubFolder\File.extension*. Absolute paths can start with a backslash (\), as in: *MainFolder\SubFolder\File.extension*.

Notes:

- To avoid import errors, run a load file precheck via the Precheck Load File button to validate whether the native file paths are correct and that linked native files exist and are accessible.
- Currently, the application does not check if duplicate native file paths are in the load file.
 Therefore, you may want to manually review your load file data to ensure there are no duplicated file paths before starting an import job. Duplicated native file paths do not cause import errors, but they may lead to billing consequences.
- 6. Folder Info—builds the folder browser structure for the documents.
 - This field is backslash "\" delimited.
 - If not set, the documents load to the root of the case.
 - Each entry between backslashes is a folder in the system's folder browser.

• Each backslash indicates a new subfolder in the browser. For example, if the load file contained the following entry in the folder information field, "Slinger, Ryan\Email\deleted_items", then the software would build the following folder structure:



Each document with the above entry would be stored in the "deleted items" folder.

- 7. **Relativity Native Time Zone Offset**—RelativityOne's native viewer technology displays all email header dates and times in GMT. This numeric field offsets how email header dates and times appear in the viewer.
 - If the value in this field is blank, or 0, for a document, then the email header date and time appears in GMT.
 - You can enter a whole number in this field (positive or negative) to offset the time from GMT to the local time zone of the document. For example, if the document was collected from US CDT time, enter "-5" in the field, because the CDT offset from GMT is -5.
 - This ONLY applies when viewing email header dates and times in the RelativityOne Native File Viewer. Your metadata fields are displayed as imported.

4.2.4 Accepted date formats

RelativityOne accepts date and time as one field. For example, Date Sent and Time Sent should be one field. If date sent and time sent ship separately, you must create a new field for time. You can format date fields to accept the date without the time, but not the time without the date. Dates cannot have a zero value. Format dates in a standard date format such as "6/30/2023 1:23 PM" or "6/30/2023 13:23".

Note: To import or export data with a date/time format that differs from the US format, be sure to select the correct Regional Settings option when creating a new Import/Export job.

The table below lists the date formats recognized by Import/Export and Import Service (IAPI). It contains both valid and invalid date formats:

Entry in Load File	Object Type	Definition
Monday January 4 2023	1/4/2318 0:00	
05/28/2023 7:11 AM	05/28/2023 7:11 AM	
5.08:40 PM	6/30/2023 17:08	The current date will be entered if the date is missing. For this example, assume the import was done on 6/30/2023.
17:08:33	6/30/2023 17:08	The current date will be entered if the date is missing. For this example, assume the import was done on 6/30/2023.
17:08	6/30/2023 17:08	The current date will be entered if the date is missing. For this example, assume the import was done on 6/30/2023.

Entry in Load File	Object Type	Definition
5:08 PM	6/30/2023 17:08	The current date will be entered if the date is missing. For this example, assume the import was done on 6/30/2023.
14-Apr	4/14/2023 0:00	The current year will be entered if the year is missing.
9-Apr	4/9/2023 0:00	The current year will be entered if the year is missing.
14-Mar	3/14/2023 0:00	The current year will be entered if the year is missing.
1-Mar	3/1/2023 0:00	The current year will be entered if the year is missing.
22-Feb	2/22/2023 0:00	The current year will be entered if the year is missing.
20230420	4/20/2023 0:00	
20230420 2:22:00 AM	4/20/2023 0:00	
4/9/2023 16:13	4/9/2023 16:13	
4/9/2023 8:49	4/9/2023 8:49	
9-Apr-23	4/9/2023 0:00	
Apr. 9, 23	4/9/2023 0:00	
4.9.2023	4/9/2023 0:00	
4.9.23	4/9/2023 0:00	
4/9/2023	4/9/2023 0:00	
4;9;2023	4/9/2023 0:00	
Wednesday, 09 April 2023	4/9/2023 0:00	
12-31-2023	12/31/2023 12:00 AM	
2023-11-	11/28/2023	

Entry in Load File	Object Type	Definition
28T17:45:39.744- 08:00	0:00	
4/9/23 13:30 PM		Results in an error
2023-044-09		Results in an error
4/9/2023 10:22:00 a.m.		Results in an error
00/00/0000		Results in an error unless the CreateErrorForInvalidDate value is set to false.

4.2.5 Delimiters

During import, you can designate which delimiters are used in your load file. You can select each delimiter from the ASCII characters, 001 – 255.

The delimiter characters have the following functions:

- Column—separates load file columns.
- Quote—marks the beginning and end of each load file field (also known as a text qualifier).
- Newline—marks the end of a line in any extracted or long text field.
- **Multi-value**—separates distinct values in a column. This delimiter is only used when importing into a RelativityOne multi-choice field.
- **Nested-values**—denotes the hierarchy of a choice. This delimiter is only used when importing into a RelativityOne multi-choice field.

For example, say a load file contained the following entry, and was being imported into a multi-choice field: "Hot\Really Hot\Super Hot; Look at Later"

With the multi-value delimiter set as ";" and the nested value delimiter set as "\"", the choices would appear in RelativityOne as:



All checkboxes are automatically selected under each nested value. The full path to each multi-choice element is required. For example:

DocID	New Privilege
1	04. Redact;01. Yes\b. Solicitor/Client;

appears as:



To select "01. Yes/a. Litigation," add it to the record after ";".

4.2.6 Default delimiters

If you generate your own load files, you may choose to use the system defaults:

- **Column**—Unicode 020 (ASCII 020 in the application)
- Quote—Unicode 254 (ASCII 254 in the application)
- **Newline**—Unicode 174 (ASCII 174 in the application)
- Multi-Value—Unicode 059 (ASCII 059 in the application)
- **Nested Values**—Unicode 092 (ASCII 092 in the application)

4.2.7 ZIP archive with extracted text and natives

To import any text or native file when not using Express Transfer, you need to zip the files and upload the zip file in the Choose Load File And Location dialog in Import/Export.

The zip file structure can be either flat or hierarchical with multiple levels of sub-folders. You must ensure that file paths in the related load file match the zip file's structure.

See below for a sample of a hierarchical zip file structure and a matching load file:



[^]Control Number^|^Extracted Text^|^Native File^

^DOCUMENT

12345^|^MainFolder\SubFolderTextA\SubFolderTextB\TextFile12345.txt^|^MainFolder\SubFolderNatives\NativeFile12345.xts^

4.3 Image and extracted text files

For image imports, Import/Export requires Opticon load files with ANSI/Western European encoding. This .opt text file references the Control ID on a page level. The first page should match up to any data you intend to load. You can use this same process for importing page-level extracted text.

Import/Export does not support Unicode .opt files for image imports. When you have a Unicode .opt file, you must save it in ANSI/Western European encoding.

You must convert images in unsupported formats using a third-party conversion tool before Import/Export can successfully upload them.

4.3.1 Supported image file formats

Import/Export accepts only the following file types for image loads:

- Single page, Group IV TIF (1 bit, B&W)
- Single page JPG
- Single page PDF
- · Multi page PDF
- Multi page TIF can be imported into the system, but you must load them as native files
- · Only one PDF per document is supported

4.3.2 Load file format

The Opticon load file is a page-level load file in which each line represents one image.

A sample of Opticon load file is the following:

```
REL00001,REL01,D:\IMAGES\001\REL00001.TIF,Y,,,3
REL00002,REL01,D:\IMAGES\001\REL00002.TIF,,,,
REL00003,REL01,D:\IMAGES\001\REL00003.TIF,,,,
REL00004,REL01,D:\IMAGES\001\REL00004.TIF,Y,,,2
REL00005,REL01,D:\IMAGES\001\REL00005.TIF,,,,
```

The fields are, from left to right:

- Field One (REL00001)—page identifier.
- Field Two (REL01)—volume identifier; not required and not used in Import/Export.
- Field Three (D:\IMAGES\001\REL00001.TIF)—path to the image to be loaded.
- Field Four (Y)—document marker: "Y" indicates the start of a unique document.
- Field Five (blank)—used to indicate a folder; not required and not used in Import/Export.
- Field Six (blank)—used to indicate a box; not required and not used in Import/Export.
- Field Seven (3)—used to store page count; not required and not used in Import/Export.

4.3.3 ZIP archive with images


To import images when not using Express Transfer, you need to zip the image files and upload the zip file in the Choose Load File And Location dialog in Import/Export.

The zip file structure can be either flat or hierarchical with multiple levels of sub-folders. You must ensure that image file paths in the related load file match the zip file's structure.

4.3.4 Importing extracted text during an image load

You can also import extracted text during the image import process by setting an option in Import/Export. For more information about importing extracted text during an image load, see Importing an image file via Import/Export.

No changes are needed in the Opticon load file. If the aforementioned setting is active, Import/Export looks for page level .txt files that are named identically to their corresponding TIF files. For example:



4.4 Processed data

Some data originates from client files and needs processing to extract the metadata. The following table shows the delimiters that your internal processing software must use to present data as fields.

Value	Character	ASCII Number
Column	¶	020
Quote	þ	254
Newline	®	174
Multi-Value	,	059
Nested Value	\	092

You can provide this list to your vendor to help communicate the required delivery format for load files. The fielded data should be delivered as delimited files with column or field names located in the first line.

```
pControl Numberp@ 1pAttachmentp@ 1pAttachment Parent IDp@ 1pAuthorp@ 1pAttachmentp@ 1pAttachmentp
pameyers 0000003p0c4pp0c4pp0c4pp0c4pp0c4pp0c4pp0c4pp0c4pp0c4pp0c4pb.Petersonp0c4p01c9D027DAB52FC39F778516475E
pameyers_0000006pccopp@copp@copp@copp.60pp@copp@copporare;pccopp@copp@copporare;pccopp@copp@copporare;pccopp@copp@copporare;pccopp@copp@copporare;pccopp@copp@copporare;pccopp@copporare;pccopp@copp@copporare;pccopp@copp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopp@copporare;pccopporare;pccopp@copporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporare;pccopporar
pAMEYERS_0000007p@@pp@@pp@@ppp@@pp.69p@@pp@@pNon Responsive;p@@pp@@pInfo on some cuts for 05
pameyers_0000008p@@pp@@pp@@pp@@pp@@pp@@pp.64p@@pp@@pp@esponsive;p@@@pp@@pTApTA #22872p@@@p01C9D027B28A4
pAMEYERS_0000011p@@pp@@pp@@dpp@@dpp@@dp0.76p@@dpp@@dpResponsive;p@@dpp@@dpAccomplishments and Goals 20
pamEYERS_0000012pmcdppmcdppmcdppmcdppmcdp0.77pmcdppmcdpResponsive;pmcdppmcdpLV Cogen cut for HE 19pmcdp0
pameyers_0000013p@@pp@@dpp@@dpp@@dpp@@dp0.83p@@dpp@@dpNon Responsive;p@@dpp@@dpCut on TAG 23841p@@dp010
pameyers 0000014p033pp033pp033pp033pp033pp033p0.89p033pp033pnon Responsive;p033pp033pTAG 25883p033p01C9D027B2
pameyers_0000017p000pp000pp0000pp0000pp0000pp000pp000ppp0000ppp0000pp1000p2 4-27656p000pp01C9D027B2C0BCE9AED1
pameyers 0000018p031pp031pp031pp031pp031pp031pp031pp031pp031pp031pp031pt Cogen for 07/21/01p031pp01c9D027B2C090D68
```

4.5 Transcript file types supported

Import/Export only supports these transcript file types: .ptf, .xmptf, .rtf, .txt, .trn, and .lef. See Uploading transcripts in the User Guide for more information on transcripts.

4.6 Access DB (MDB) load file specifications

Note: The import and export workflows with Access DB (MDB) are designed for and are currently available for the Asia-Pacific region. For information on the possibility of enabling this flow in your instance, please contact your Account Representative.

In certain markets, the Import/Export supports data transfer of structured data defined in Access DB load files. The structure of the Access DB contains the following four tables.

Table Name	Table Description
Export	Main document information.
Parties	People and organization information for each document.
Pages	Listing of electronic image filenames for each document.
Export_Extras	Additional data fields for each document.

- Import workflow: Import/Export supports import from Access DB load file with .mdb or .accdb extension.
- Export workflow: Import/Export generates a single Access DB load file with .mdb extension.

4.6.1 Export table

This table holds the primary information about a document.

Field	Data Type	Explanation—Document Types and Cod- ing Method and Possible Values	If Mandatory
Document_ID	Text, 255	Uniquely identifies the document and is the link	Yes

Field	Data Type	Explanation—Document Types and Coding Method and Possible Values	If Mandatory
		to the other four tables.	
Host_Reference	Text, 255	If the document is an Attachment, this field contains the Document ID of its host document.	No, can be left blank
Document_Date	Text, 11	Dates in the format "DD-MMM-YYYY", where: • "DD" equals the day date;	Yes, if information is available
		"MMM" equals the month;	
		"YYYY" equals the year.	
		For example, 26 March 2017 would be represented as "26-Mar-2017".	
Estimated	Text, 3	The estimated date for a document (for example: YES, NO, Y, N).	No
Document_Type	Text, 255	The document type (for example: letter, minutes, maintenance reports, etc.).	No
Title	Text, 255	The title for a document.	No
level_1	Text, 20	The Party level of the Document ID.	Yes
level_2	Text, 20	The Box level of the Document ID.	No
level_3	Text, 20	The Folder level of the document ID.	No
Description	Long Text	The description for a document.	No

4.6.2 Parties Table

This table holds the names of people associated with a particular document and their relationship to the document. It may also hold organization information for these people.

There is a one-to-many relationship between the Export table containing the primary document information and the Parties table, because multiple people could be associated with a single document.

Field	Data Type	Explanation	If Mandatory
Document_ID	Text, 255	Identifies the document (related to the Export table via the Document_ID field).	Yes
Correspondence_ Type	Text, 100	Correspondence Type (for example: To, From, CC, BCC).	Yes
Persons	Text, 255	Hard copy—information from the face of the document in the format "Last Name, First Name" or "Last Name, Initial".	No
		Emails and other electronic files—information should be in the format as extracted from the document metadata.	

Field	Data Type	Explanation	If Mandatory
Organisations	Text, 255	The organization information from the face of the document or extracted from the document metadata.	

Note: Persons and Organisations fields are treated as a single value on import with the correspondence type as <Correspondence_Type>_Persons_and_Organisations. This way it can be imported into a single workspace field on the import. That allows you to select it on export as a single value as well. Example value: Last Name, First Name [Organisation].

4.6.3 Pages table

There will be an entry in the Pages table for every TIFF page, text, or PDF document that relates to a single document in the Export table.

There is a one-to-many relationship between the Export table and the Pages table. Where Native Electronic Documents only are exchanged, no TIFF, text, PDF files or placeholder pages, there will only be one entry in the Pages table corresponding to each Native Electronic Document.

Field	Data Type	Explanation	If Mandatory
Document_ID	Text, 255	Identifies the document (related to the Export table via the Document_ID field).	Yes
Image_File_Name	Text, 128	Filename, including extension of each indexed document.	Yes
page_label	Text, 32	Label for each document (for example: Native, Text, PDF, or Document ID).	Yes
page_num	Number, Double	An integer indicating the order in which the files related to the Document ID should be sequenced when viewing the full document.	Yes
num_pages	Number, Long Integer	The number of pages in the file. For rendered PDF files, this will be the number of pages in the PDF. For native electronic files (including native PDF files), this will be set to "1".	No

4.6.4 Export_Extras table

This table holds any additional metadata the parties wish to exchange that is not held in the other three tables.

Field	Data Type	Explanation	If Mandatory
Document_ID	Text, 255	Identifies the document (related to the Export table via the Document_ID field).	Yes
theCategory	Text, 50	Identifies the data type (supported types currently are: TEXT, NUMB, BOOL, DATE, PICK, MEMI).	Yes

Field	Data Type	Explanation	If Mandatory
theLabel	Text, 255	The name of the field.	Yes
theValue	Text, 255	If not Memo, Custom Field Data.	No if MEMO category
memoValue	Long Text or Text fixed- length setup as length > 255	If Memo, Custom Field Data.	No if not MEMO category

4.6.5 Example of values in Export Extras table

This table presents exemplary values in Export Extras table.

theLabel	theCategory	theValue or memoValue	Explanation
File Name	TEXT	Monthly Reports.docx	For all electronic files, the original filename (including extension).
MD5	TEXT	08a008a01d498c404b0c30852b39d3b8	The MD5 (a message- digest algorithm) hash value of the file.
Sent Date/Time	DATE	26/05/1999 8:33 PM	The date and time the email was sent.

4.6.6 Export recommendations

If you need to export a date with the time zone and have the date formatted "Day name, DD Month YYYY hh:mm:ss TZ", for example, "Thursday, 28 June 2012 6:29:00 PM (UTC+10:00) Canberra, Melbourne, Sydney", include the Time Zone Field in the Export_Extras at the time of export.

If you need to add the num_pages to the Pages table for PDF documents, include the Relativity PDF Page Count field to the Export_Extras at the time of export.

As the Import/Export generates a single Access DB load file, consider splitting the large volumes of export data into smaller jobs, and select the option to extract long text field, for example Extracted Text, to a separate file. The MDB file limit is 2GB for the load file, excluding: external file exported as native, images, PDF, extracted text.

5 General recommendations for structured data import and export jobs

The following are recommendations for importing and exporting load files.

5.1 Load file import recommendations

- Use Pre-check Load File feature to validate load file data before executing the import job. We strongly
 recommend using this feature to ensure that the import job doesn't encounter metadata errors. If your
 workflow uses Staging, the Pre-check Load File step won't be available. In such case, validate your
 load file manually before proceeding.
- When using Import/Export in <u>web only mode</u>, ensure that the full path listed in the load file is captured in the ZIP file.
- Try to limit the number of fields in a single import job to 100 to minimize risk of job failure due to SQL exception related issues.
- When importing new choice fields, you may experience the unexpected behaviors, such as errors
 occurring when importing choice fields or slow import jobs for choice fields. To help prevent these
 issues, try to limit the number of choice values in a single import job to 100. This number indicates the
 maximum of new values in all choice type fields across the entire set of records.
- · Extracted Text import:
 - There is no limitation or performance impact related to size of extracted text when the import is performed to Data Grid.
 - Performance and stability are affected for extracted texts import to SQL. If there is no other option and you must use SQL, please import extracted text separately from other data fields.
 - Depending on the job configuration, the extracted text import to Data Grid is 60-80% faster than similar import to SQL.
 - Performance improves when extracted text files use UTF-16 encoding.

5.2 Load file export recommendations

- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths. You may receive an error message: "The compressed (zipped) folder is invalid." In such case, you can do the following:
 - Use Express Transfer to export the dataset to your local disk without creating an archive.
 - Use other tools to extract the archive or move the archive file to a different location on your local machine.
 - Group files by "File Type" and not "Workspace Structure". This may shorten the folder structure inside the archive file.

- Depending on the exported data structure, a Workspace folder structure can degrade performance significantly, up to 30 times slower in edge cases. We recommend using the File Type folder structure.
- Exporting numerous fields with complex data structures may affect performance or cause job errors. We recommend exporting only necessary fields.
- Increasing the Max Files above 10,000 per folder may lead to significant export performance degradation. We recommend using the default setting of the Max Files per folder=2,000.
- The default Max (Volume) Size is set to 6,000 MB. You can adjust this setting to any value that works best for you. Setting it higher than the default value does not impact the export performance.
- Exporting images as PDFs or multi-page TIFFs is slower than exporting them as single page images.
- Exporting to a ZIP archive using Import/Export in web only mode is significantly slower than exporting data with Express Transfer or exporting data to the Staging only.
- Exporting text files in Unicode (UTF-16) encoding is faster than in other encodings.

6 Express Transfer overview

Express Transfer is an integral part of Import/Export workflows when <u>activated</u> for use with Import/Export. Using Import/Export *with* Express Transfer active is the recommended method of transferring data in Relativity. It can be used to transfer any data size, but it's designed especially for transferring large structured and unstructured data files greater than 20GB.

Using Import/Export with Express Transfer active helps reduce the time and effort it takes to transfer data in Relativity. For additional information on performance considerations when transferring data using desktop applications, see Data transfer performance considerations on page 47.

Express Transfer is a separately <u>installed</u> desktop application that operates outside of RelativityOne. Although you are accessing and using Import/Export within RelativityOne to process transfer jobs, it is the activated Express Transfer application that is handling the actual data transfer (upload and download) process in the background to and from RelativityOne and the staging area or local disk. It uploads (imports) a single job at a time and downloads (exports) up to five concurrent jobs at a time on a single client machine. You can have multiple users running jobs on multiple machines without conflict.

Monitoring import and export job transfers is done through the Express Transfer application as well as from the Import/Export Jobs page.

To ensure that you always have the most recent version and features of Express Transfer, the default update setting is configured to automatically prompt you when a new version is available. We recommend keeping this setting enabled. See <u>Installing and updating Express Transfer desktop application on page 33</u> for more information. You can manually check for updates anytime by right-clicking the Express Transfer icon in your system tray. See <u>Express Transfer system tray menu on page 49</u> for more information.

6.1 Prerequisites

To use Import/Export with Express Transfer, complete the following in this order:

- 1. Install Import/Export application from the Application Library in the workspace. Refer to Installing Import/Export for more information.
- 2. Install Express Transfer desktop application on your computer. Refer to Installing Express Transfer for more information.
- 3. Activate Express Transfer within Import/Export. Refer to Activating Express Transfer for more information.

6.2 Considerations when to use and not use Express Transfer with Import/Export

We recommend using Import/Export *with* Express Transfer activated whenever possible for all importing and exporting workflows, and particularly when:

- data file size is greater than 20GB, although Express Transfer can be used for any size data transfer.
- processing multiple import jobs. The jobs will be queued and executed when the previous job is complete.
- slow or unstable network connection. Express Transfers enables you to retry the upload.

Use Import/Export without activating Express Transfer when:

- · your company policy prohibits installing desktop applications.
- your network configuration does not allow third party applications to send or receive data, such as proxy settings.
- · data file size is less than 20GB.
- · data is in ZIP files.

Note: You need to use Express Transfer to upload and process encrypted materials, such as password-protected zip files or Case files (L01/N01) that require Password Bank functionality. If you cannot use Express Transfer for such imports, zip your encrypted materials in a single unencrypted ZIP container. The 20 GB limit for the zip file size applies. Import/Export will transfer and extract the top-level zip file, preparing your encrypted materials for Processing. Then, Processing will utilize Password Bank to decrypt materials.

6.3 Express Transfer overview

Express Transfer is an integral part of Import/Export workflows when <u>activated</u> for use with Import/Export. Using Import/Export *with* Express Transfer active is the recommended method of transferring data in Relativity. It can be used to transfer any data size, but it's designed especially for transferring large structured and unstructured data files greater than 20GB.

Using Import/Export with Express Transfer active helps reduce the time and effort it takes to transfer data in Relativity. For additional information on performance considerations when transferring data using desktop applications, see <u>Data transfer performance considerations on page 47</u>.

Express Transfer is a separately <u>installed</u> desktop application that operates outside of RelativityOne. Although you are accessing and using Import/Export within RelativityOne to process transfer jobs, it is the activated Express Transfer application that is handling the actual data transfer (upload and download) process in the background to and from RelativityOne and the staging area or local disk. It uploads (imports) a single job at a time and downloads (exports) up to five concurrent jobs at a time on a single client machine. You can have multiple users running jobs on multiple machines without conflict.

Monitoring import and export job transfers is done through the Express Transfer application as well as from the Import/Export Jobs page.

To ensure that you always have the most recent version and features of Express Transfer, the default update setting is configured to automatically prompt you when a new version is available. We recommend keeping this setting enabled. See Installing and updating Express Transfer desktop application on the next page for more information. You can manually check for updates anytime by right-clicking the Express Transfer icon in your system tray. See Express Transfer system tray menu on page 49 for more information.

6.3.1 Prerequisites

To use Import/Export with Express Transfer, complete the following in this order:

- 1. Install Import/Export application from the Application Library in the workspace. Refer to Installing Import/Export for more information.
- 2. Install Express Transfer desktop application on your computer. Refer to Installing Express Transfer for more information.

3. Activate Express Transfer within Import/Export. Refer to Activating Express Transfer for more information.

6.3.2 Considerations when to use and not use Express Transfer with Import/Export

We recommend using Import/Export *with* Express Transfer activated whenever possible for all importing and exporting workflows, and particularly when:

- data file size is greater than 20GB, although Express Transfer can be used for any size data transfer.
- processing multiple import jobs. The jobs will be queued and executed when the previous job is complete.
- slow or unstable network connection. Express Transfers enables you to retry the upload.

Use Import/Export without activating Express Transfer when:

- · your company policy prohibits installing desktop applications.
- your network configuration does not allow third party applications to send or receive data, such as proxy settings.
- · data file size is less than 20GB.
- · data is in ZIP files.

Note: You need to use Express Transfer to upload and process encrypted materials, such as password-protected zip files or Case files (L01/N01) that require Password Bank functionality. If you cannot use Express Transfer for such imports, zip your encrypted materials in a single unencrypted ZIP container. The 20 GB limit for the zip file size applies. Import/Export will transfer and extract the top-level zip file, preparing your encrypted materials for Processing. Then, Processing will utilize Password Bank to decrypt materials.

6.4 Installing and updating Express Transfer desktop application

The Express Transfer application must be installed on your computer in order to use it with Import/Export workflows. The instructions below can be used for both Microsoft Windows and Apple macOS installations. You can configure preferences to automatically check for new software versions or you can check for them manually. We recommend keeping the default setting to enable the system to automatically check for new software versions to ensure you're using the latest software features available.

For additional information on performance considerations when transferring data using desktop applications, see Data transfer performance considerations.

6.4.1 Requirements

Refer to the sections below for the necessary requirements for Express Transfer.

6.4.1.1 System requirements

To use Express Transfer, your computer must meet the following minimum system requirements:

System Configuration	Requirement
Operating system	MS Windows 10, MS Windows 11, or Apple macOS
Windows Server operating system	Windows Server 2019 or Windows Server 2022
System memory	4 GB RAM, recommended 8 GB RAM

6.4.1.2 Port access

Express Transfer requires TCP port 443 to be open in order for it to operate. For more specific information about port considerations relating to Express Transfer, please see our <u>Data Transfer Tools: Required Port Considerations for RelativityOne (Import/Export, Express Transfer, ROSE and Migrate)</u> article in the Relativity Community.

6.4.2 Prerequisites

To use Express Transfer, complete the following in this order:


- 1. Install Import/Export application from the Application Library in the workspace. Refer to Installing Import/Export for more information.
- 2. Install Express Transfer desktop application on your computer. Refer to Installing Express Transfer for more information.
- 3. Activate Express Transfer within Import/Export. Refer to Activating Express Transfer for more information.

6.4.3 Installing Express Transfer

To install the Express Transfer application on your computer for use with Import/Export:

- 1. Navigate to the Import/Export Job page.
- 2. Click the **New Import/Export Job** button.

3. Depending on the operating system used, click the **Windows** or **MacOS** button to download the installer file.




4. For macOS systems, you need to have administrative privileges to use and install the software, as well as to receive automatic software updates. On the Installer dialog, enter your user name and password, then click **Install Software**.




- 5. Navigate to the folder on your computer where the installer file was downloaded. Depending on the operation system, double-click one of the following files to begin the installation process:
 - For Windows OS: Express Transfer Setup.exe
 - For macOS: Express Transfer Setup.pkg
- 6. Click one of the options on the Select Setup Install Mode dialog:
 - **Install for me only (recommended)**—enables Express Transfer to be used by your account only.

- **Install for all users**—enables Express Transfer to be used by anyone who logs on to this computer. You will need Admin credentials to select this option.
- 7. Click Next.
- 8. Use the default destination folder already displayed or click **Browse** to select a different location for the Express Transfer application.
- 9. Click Next.
- 10. (Optional) On the Select Additional Tasks dialog, do any of the following:
 - Autostart Express Transfer on system startup—select this check box to automatically launch the Express Transfer application each time your computer starts. Leave it blank if you want to manually launch Express Transfer when you want to use it.
 - Create a desktop shortcut—select this checkbox to create a shortcut icon on your desktop for Express Transfer. Otherwise, leave it blank.
- 11. Click Next.
- 12. Click Install on the Ready to Install dialog to begin the installation process.
- 13. When the installation is complete, click **Finish**to close the installation wizard. Express Transfer is now installed. To use Express Transfer for import and export workflows, you must activate it within Import/Export. See <u>Activating Express Transfer</u> for more information.



If you selected the Run Express Transfer checkbox on the finish setup dialog of the wizard, the Express

Transfer application will open and its icon will be available in the system tray. Right-click on the icon to display an application menu with these options:



- Connectivity check—choose this option to check if Express Transfer is successfully accessing the
 Internet and the Import/Export application. See Express Transfer Connectivity check for more information.
- Show logs—choose this option if instructed to do so by Relativity Support to investigate or troubleshoot an issue with Express Transfer transaction logs and text files. File explorer will open the logs folder on your local drive. For example, C:\Users\<username>\AppData\Local\Express Transfer\logs. With Express Transfer open, you can also press F8 to display the logs folder.
- Check for Updates—choose this option if you want to manually check to see if your version is up-todate or if a new version of Express Transfer is available. See Manually checking for software updates on page 43 for more information.
- **Preferences**—choose this option to modify the application settings. You can also view the software version number from this dialog.
- Quit—choose this option to completely exit the Express Transfer application. The Express Transfer icon will no longer be displayed in the system tray. To reopen Express Transfer, double-click on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.

6.4.4 Silent installation of Express Transfer

In some organizations, the IT department or System Administrator may be the one to install the Express Transfer desktop application installer file behind the scenes over a network instead of having each end user do it themselves on their individual desktop. This method is often referred to as a silent, or unattended, installation because it requires no end user interaction with the installation wizard. The Express Transfer end user is not aware that the installation process is occurring. Typically, this type of installation is used in large enterprise organizations to help control the software installation process to ensure that it's done consistently so that all users have the same installation configuration.

When installing Express Transfer from command line tools, we support silent and verysilent mode:

• /silent—this option displays the installation wizard as it goes through the installation process. All the default options are automatically selected.


• /verysilent—this option does not display the installation wizard as it goes through the installation process. All default options are selected automatically.

Prerequisites

- Administrator rights to run the command prompt.
- Knowledge of how to use command line interface (CLI) tools.
- Obtain the downloaded Express Transfer installer file for Windows OS, which is Express Transfer Setup.exe. See <u>Installing Express Transfer</u> for more information on how to download the file using the Import/Export application.


6.4.5 Locating the Express Transfer version number


The Express Transfer version number is displayed at the bottom of the **In Progress** and **History** tabs within the application.



You can also find it in the bottom left corner of the Preferences dialog by right-clicking on the Express

Transfer icon in the system tray and selecting Preferences.






The Express Transfer software version number is contained in the first few numbers after the "v", for example "v2.49.0." The numbers after the hyphen are session identifiers that change each time you launch Express Transfer after quitting the application. These numbers may be used by Customer Support if you encounter a problem with the software. You can disregard them otherwise.

6.4.6 Automatically checking for software updates


You can configure whether or not you want the system to automatically check for new software versions of Express Transfer each time it opens and notify you with a message box. By default, this feature is enabled in Express Transfer Preferences. We recommend that you keep it enabled to ensure your system is running the latest software version containing the most recent software features available. If you choose to change this default setting, you will need to use the Check for Updates option in the Express Transfer system tray. See Manually checking for software updates on page 43 for more information.

To automatically check for software updates:

1. Right-click on the **Express Transfer** icon in your system tray.



2. Click Preferences.




3. By default, the **Check for Updates** is toggled on. If you do not want the system to automatically check for updates and notify you, toggle it off.

Note: We do not recommend turning this option off. If it is off, your Express Transfer version may not contain the latest features. If it is off, you will need to regularly use the Check for Updates option in the Express Transfer system tray to determine if your software version is current. See Manually checking for software updates on the next page for more information.


- 4. Click **Save** after updating the setting.
- 5. To apply any changes made to Preferences, quit the Express Transfer application by right-clicking on

the Express Transfer icon in your system tray and clicking Quit.




6. Reopen the application by double-clicking on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.

Whenever a new version is available, you'll be notified with an Application update dialog displaying the new version number available and release notes for it. Click **Update now** to download the new version's executable file, and then follow the <u>Installing Express Transfer on page 34</u> steps to finish installing the update on your system.




6.4.7 Manually checking for software updates

You can check for software updates anytime by right-clicking on the **Express Transfer** icon in your system tray and clicking **Check for Updates**. If your software version is current, a message is displayed letting you know it's up-to-date.



If a new version is available, the Application update window displays the new version number available and release notes for it. Click **Update now** to download the new version's executable file, and then follow the Installing Express Transfer on page 34 steps to finish installing the update.



6.5 Activating and deactivating Express Transfer

You have the ability to activate and deactivate Express Transfer for use with Import/Export. However, the recommended method for transferring data is with Express Transfer activated.

6.5.1 Prerequisites

To use Express Transfer, install the following in this order:

- 1. Install Import/Export application from the Application Library in the workspace. Refer to Installing Import/Export for more information..
- 2. Install Express Transfer desktop application on your computer. Refer to Installing Express Transfer for more information

6.5.2 Considerations when to use and not use Express Transfer with Import/Export

We recommend using Import/Export with Express Transfer activated whenever possible for all importing and exporting workflows, and particularly when:

- data file size is greater than 20GB, although Express Transfer can be used for any size data transfer.
- processing multiple import jobs. The jobs will be queued and executed when the previous job is complete.
- slow or unstable network connection. Express Transfers enables you to retry the upload.

Use Import/Export without activating Express Transfer when:

- · your company policy prohibits installing desktop applications.
- your network configuration does not allow third party applications to send or receive data, such as proxy settings.
- · data file size is less than 20GB.
- · data is in ZIP files.


Note: You need to use Express Transfer to upload and process encrypted materials, such as password-protected zip files or Case files (L01/N01) that require Password Bank functionality. If you cannot use Express Transfer for such imports, zip your encrypted materials in a single unencrypted ZIP container. The 20 GB limit for the zip file size applies. Import/Export will transfer and extract the top-level zip file, preparing your encrypted materials for Processing. Then, Processing will utilize Password Bank to decrypt materials.

6.5.3 Activating Express Transfer

To use Import/Export with Express Transfer, you need to activate Express Transfer. Once activated, it will remain active until your Relativity session ends or until you deactivate it.


To activate Express Transfer for use with Import/Export:

- 1. Navigate to the Import/Export Job page.
- 2. Click the **New Import/Export Job** button to start a new job.
- 3. Click **Activate** on the Choose workflow dialog to activate Express Transfer.



4. If a browser message box appears asking to allow the site to open Express Transfer, click **Open Link** to proceed with activating Express Transfer. If you do not, then Express Transfer will not be activated.

Note: To always allow your system to open the link to Express Transfer, select the "Always allow" checkbox, and the message box will not appear anymore.




Note: If the activation process fails, click the **Complete activation** button on the message that appears to initiate the activation process. Refer to Express Transfer Connectivity check on page 63 for more information on connection status information.

5. When the activation process successfully completes, the Express Transfer application opens.




6. Return to the Import/Export application. The Express Transfer status will change to **Active** on the Choose Workflow dialog.

Note: The Express Transfer application will remain active until you click the Deactivate button or log out of RelativityOne. You do not need to keep reactivating it to use it. However, if you <u>deactivate</u> it or log out of RelativityOne, you will need to reactivate Express Transfer to use it again with Import/Export.



6.5.4 Deactivating Express Transfer

If you do not want to use an active session of Express Transfer with Import/Export, you can click the **Deactivate** button on the Choose Workflow dialog.



In order to use Express Transfer again with Import/Export, you will need to reactivate it.

6.5.5 Data transfer performance considerations

There are many variables that can degrade or improve the performance of data transfers for desktop applications, such as Express Transfer. Transfer rates when using desktop applications are influenced by several variables and results may vary based on factors such as RAM, CPU, local drive specifications, network drive specifications, and available bandwidth at the time of the transfer.

Review the list of performance considerations below before beginning to use Express Transfer.


If you experience issues despite following the information below, please contact <u>Support</u> for assistance. For additional information, refer to the Community article <u>Performance considerations</u> for data transfers.

- Run on local machine: Express Transfer has been designed and tested as a desktop application being run on a user's local machine.
- Read access: Ensure that Express Transfer has read access to all files/folders. Remove system / hidden attributes.
- **Port 443:** Ensure that port 443 is open and is not blocked or traffic is restricted to it. See the Community article Performance considerations for data transfers for more information.
- **Internet connection:** Use a strong and stable internet connection for data transmission. Wi-Fi is not recommended.
- Internet speed: Transfer speeds are dependent on your internet speeds. Check your internet connection using <u>Speedtest</u> or any other bandwidth testing website. Make note of the upload speed in megabits per second. Also refer to Express Transfer <u>Limit bandwidth</u> setting if needed.
- Local storage speed: Transfers from network drives or external disks, such as thumb drives/USB drives, will degrade performance and/or cause issues maintaining a connection. It is most effective to copy data to and from a fast local storage.
- **Local machine specs:** Ensure your local machine and browser adheres to the Express Transfer minimum system requirements and is operating the latest version of the software.
- Level of data fragmentation: Due to bandwidth sharing, avoid performing large and fragmented transfers in parallel. The more fragmented the dataset, the lower the transfer performance.
- **Concurrent transfers:** Number of concurrent transfers that are happening at the same time within the network by various tools, services, and users.
- **Concurrent utilization:** Level of concurrent utilization of the user's computer resources, that is CPU, RAM, I/Os, by other processes on that computer.
- **Compressed datasets:** Avoid compressing datasets with ZIP, 7z, etc. The faster transfer time due to fewer multi-part files is negated by the time and effort to compress and decompress data. However, compressing datasets without decompressing in the destination folder (staging directory) can be considered when all the following are true:
 - · Dataset consist of fragmented data
 - Destination folder is a Processing source location
 - The dataset uploaded is going to be processed by Relativity Processing
- VPN usage: Using a VPN can potentially slow down internet traffic. When workstations use a VPN session, it can interfere with transfers from that workstation. RelativityOne is hosted in a public cloud and does not require VPN to use. See the Community article Performance considerations for data transfers for more information.
- Traffic monitoring and data protection software: These types of software tools influence data transfer. See the Community article <u>Performance considerations for data transfers</u> for more information on each of these:

- Firewall: Firewall configuration may require special tuning to use the Express Transfer.
- Antivirus software: Antivirus software may disrupt the transfer protocol in Express Transfer.
- **Anti-malware software:** An exception should be created for Express Transfer in Windows Defender or in other anti-malware software installed on the user's machine.

6.6 Express Transfer system tray menu

Once the Express Transfer application is installed, its icon will be available in the system tray. Right-click on the icon to display an application menu with these options:



- Connectivity check—click this option to check if Express Transfer is successfully accessing the
 Internet and the Import/Export application. See Express Transfer Connectivity check for more information.
- Show logs—click this option if instructed to do so by Relativity Support to investigate or troubleshoot an issue with Express Transfer transaction logs and text files. File explorer will open the logs folder on your local drive. For example, C:\Users\<username>\AppData\Local\Express Transfer\logs. With Express Transfer open, you can also press the F8 key on your keyboard to display the logs folder.
- Check for Updates—click this option if you want to manually check to see if your version is up-to-date or if a new version of Express Transfer is available. See Manually checking for software updates on page 43 for more information. If you do not have Express Transfer Preferences set to auto-matically check for updates, you will need to use this option frequently to ensure your version of Express Transfer is the most current one available. We recommend keeping the Check for updates option in Express Transfer Preferences toggled on. See Installing and updating Express Transfer desktop application on page 33 for more information.
- **Preferences**—click this option to modify the application settings. You can also view the software version number from this dialog. See Express Transfer Preferences below for more information.

• Quit—choose this option to completely exit the Express Transfer application. The Express Transfer icon will no longer appear in the system tray. To reopen Express Transfer, double-click on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.

6.7 Express Transfer Preferences


Use Express Transfer Preferences to modify the Check for Updates setting, to limit bandwidth, to exclude temporary Microsoft Office files from data import, and to configure proxy settings.

6.7.1 Automatically checking for software updates


You can configure whether or not you want the system to automatically check for new software versions of Express Transfer each time it opens and notify you with a message box. By default, this feature is enabled in Express Transfer Preferences. We recommend that you keep it enabled to ensure your system is running the latest software version containing the most recent software features available. If you choose to change this default setting, you will need to use the Check for Updates option in the Express Transfer system tray. See Manually checking for software updates on page 43 for more information.

To automatically check for software updates:

1. Right-click on the **Express Transfer** icon in your system tray.



2. Click Preferences.




3. By default, the **Check for Updates** is toggled on. If you do not want the system to automatically check for updates and notify you, toggle it off.

Note: We do not recommend turning this option off. If it is off, your Express Transfer version may not contain the latest features. If it is off, you will need to regularly use the Check for Updates option in the Express Transfer system tray to determine if your software version is current. See Manually checking for software updates on page 43 for more information.


- 4. Click **Save** after updating the setting.
- 5. To apply any changes made to Preferences, quit the Express Transfer application by right-clicking on

the Express Transfer icon in your system tray and clicking Quit.



6. Reopen the application by double-clicking on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.

Whenever a new version is available, you'll be notified with an Application update dialog displaying the new version number available and release notes for it. Click **Update now** to download the new version's executable file, and then follow the Express Transfer Preferences on page 50 steps to finish installing the update on your system.




6.7.2 Limit bandwidth


Some organizations may have slow internet speeds and experience issues with transfer job stability causing jobs to fail due to connection timeouts. In this situation, the organization may want to limit bandwidth so that it's shared with Import/Export transfers and other business activities. This may help improve the efficiency and stability of job transfers. You can limit the bandwidth in Express Transfer by toggling on the **Max upload speed** and **Max download speed** options in Preferences. When this option is on, Express Transfer job transfers will be slower, but more stable.

To configure Limit bandwidth settings:

1. Right-click on the **Express Transfer** icon in your system tray.




2. Click Preferences.



Note: We recommend that you measure your internet connection using an online speed test before specifying the maximum speeds.


Note: If you enter a value higher than your current throughput for Limit bandwidth settings, values in the fields are set to your maximum internet speed throughput.

3. The **Max upload speed** and **Max download speed** options are off by default. If you want to turn any of them on, click the toggle. Then, enter maximum upload speed and/or maximum download speed.



- 4. Click **Save** after updating the settings.
- 5. To apply any changes made to Preferences, quit the Express Transfer application by right-clicking on


the Express Transfer icon in your system tray and clicking Quit.



6. Reopen the application by double-clicking on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.

6.7.3 Exclude temporary Microsoft Office files from data import


Whenever you open a Microsoft Office file, a temporary file is created which contains a ~ (tilde) sign at the beginning of the file name. When you're importing unprocessed data for Processing and selecting the data source on the Create Processing Job dialog, these temporary files will be displayed in the file list and will also be included in the data import process.




To prevent these temporary files from being included in the import process, the **Exclude temporary file(s)** option defaults to the On position in Express Transfer Preferences. If you wish to change that setting and include those temporary files, refer to the steps below.

To include temporary Microsoft Office files in import jobs:

1. Right-click on the **Express Transfer** icon in your system tray.




2. Click Preferences.



- 3. The **Exclude temporary file(s)** option is on by default. If you wish to turn the option off, click the toggle.
- 4. Click Save after updating the setting.
- $5. \ \ \, \text{To apply any changes made to Preferences, quit the Express Transfer application by right-clicking on}$

the Express Transfer icon in your system tray and clicking Quit.



6. Reopen the application by double-clicking on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.


6.7.4 Configuring proxy settings

If your organization or IT department requires using Express Transfer with a proxy server, follow the steps below to set up the necessary credentials. Contact your IT Department for the required information


Note: The port number used in the steps below will be different from Port 443, which is still required to be open regardless of this proxy configuration. See Port access on page 34 for more information.

To configure proxy settings:

1. Right-click on the **Express Transfer** icon in your system tray.




2. Click Preferences.



- 3. The **Proxy settings** option is off by default. If you wish to turn the option on, click the toggle, and then enter the necessary information for the following fields. Contact your IT Department for the correct information:
 - Proxy address (required)
 - Port (required)
 - Username
 - Password
- 4. Click **Save** after updating the setting.
- 5. To apply any changes made to Preferences, quit the Express Transfer application by right-clicking on

the Express Transfer icon in your system tray and clicking Quit.



- 6. Reopen the application by double-clicking on its desktop shortcut, if you saved one for it, or select it from your computer's list of programs.
- 7. Perform a <u>Connectivity Check</u> to make sure Express Transfer is connected to the Internet. If not, then the proxy settings are incorrect and will need changed.

6.8 Express Transfer Connectivity check

Connectivity check ensures that the Express Transfer desktop application authenticates and successfully accesses the Internet, the necessary ports, and the Import/Export application to transfer data. This check executes automatically when you activate Express Transfer from the Import/Export application within RelativityOne. You can also manually perform a connectivity check anytime, even when there are active transfers.

The following checks occur during the connectivity check process:

Connectivity Check	Description
Internet con- nection	This step confirms your system is connected to the internet. If this step fails, there is either no internet connection available or the proxy or firewall is blocking the connection for Express Transfer. Please contact your IT department for help.
Access to Express Trans- fer gateway	This step confirms Express Transfer successfully set up all ports needed to connect to your specific region. If this step fails, please contact your IT department for help.
Connection with Express Trans- fer infra- structure	This step confirms Express Transfer successfully connected to the infrastructure specific to your RelativityOne region. If this step fails, please contact your IT department so they can verify the correct port configuration. For more information, refer to Data Transfer Tools: Required Port Considerations for RelativityOne (Import/Export, Express Transfer, ROSE and Migrate) article in Community.
Activation status	This step confirms Express Transfer is active. If it fails, see Activating and deactivating Express Transfer for more information on reactivating it.
Connection with Import/Export	This step confirms Express Transfer is communicating with Import/Export in RelativityOne.


Note: If you perform a connectivity check before activating Express Transfer in Import/Export, only the

Internet connection is checked and the others display the no connectivity must be <u>active</u> to perform the full connectivity check.

icon. Express Transfer

To manually run a connectivity check, use any of these methods:

• From the System tray: Right-click on the icon in the desktop system tray and choose Connectivity check from the pop-up menu.




• From within Express Transfer: Click the circled check mark icon at the bottom of the Express Transfer application.



The test results are displayed after each process completes. The word "Successful" appears when all connections are working properly. If any of the system checks fail, Express Transfer will not work.

Click the Check again button to refresh the connection in the event you lose connectivity.

Note: If the "Activation status" test fails, the **Activate** button will appear next to an inactive **Check again** button. Click the **Activate** button to try to activate Express Transfer again.



Icon legend:

\bigcirc	icon indicates the connectivity test was successful
------------	---

icon indicates the connectivity test failed.

icon indicates the connectivity test is in progress.

icon indicates the connectivity test was not performed on this item. *Tip:* If this is displayed, double check to be sure Express Transfer is active in Import/Export.

6.8.1 Network Throughput Check

If there are issues with your network speeds and connectivity, a notice is displayed next to the Connectivity check icon to notify you that the network connection is poor and this may cause slow transfer speeds. Check your internet connection or consult your IT department for further assistance.

6.9 Express Transfer Job tracking and history

You can track the progress and history of jobs that were started with Express Transfer without logging into RelativityOne.

To do so, open Express Transfer by double-clicking the shortcut on your desktop.

Note: Once the job is running using Express Transfer, you can close the Import/Export application, if desired, and the transfer job will continue and not be affected. You can monitor the job using the steps below. You do not have to be logged into RelativityOne to view information within the Express Transfer application.


6.9.0.1 Prerequisites

To use Express Transfer, the following must be completed in this order:

- 1. Import/Export application must be installed in the workspace from the Application Library. Refer to Installing Import/Export for more information.
- 2. Express Transfer desktop application must be installed on your computer. Refer to Installing Express Transfer for more information.
- 3. Express Transfer must be activated within Import/Export. Refer to Activating Express Transfer for more information.

6.9.0.2 In Progress Tab

The In Progress tab displays ongoing transfer information. With Express Transfer, on a single client machine you can have one import (upload) job at a time and up to five concurrent export (download) jobs at a time. For uploads, the jobs will be queued on the client machine.




- Job Name—displays the name of the job. Click the job name to view more information about the job on the Job Details window. Or, click the Actions button next to the transfer line, then click View details. See Viewing and copying details of Express Transfer jobs.
- Transfer progress bar—displays the percentage of transfer completion.
- Starting—this status indicates the job is beginning to transfer data.
- In Queue—this status indicates the job is waiting until the first job is complete.
- Cancel a job—to cancel a job that's in progress, click the Actions button next to the transfer line and then click Cancel.

If no transfers were triggered, the tab displays a message that there are no jobs at the moment and directs you to RelativityOne to start a new job.

To check more details about the job, visit the Import/Export Job page in RelativityOne. Refer to "Import/Export Job tracking and history" for more information.

6.9.0.3 History tab

The History tab displays information about the status of previous transfer jobs that were executed.




- Finished—a full green bar and 100% indicates that the transfer successfully finished. To view details
 about the job, click the job name link or click the Actions button next to the transfer line and then click
 View details. See Viewing and copying details of Express Transfer jobs.
- Job Failed (with red exclamation mark icon)—is displayed in red and indicates that the transfer has failed and the number of items that failed. The reason for the failure is displayed next to the icon. You can perform a manual retry for a failed transfer by clicking the Actions button next to the transfer line and then clicking Retry failed files. Jobs older than seven days cannot be restarted. See Express Transfer reporting jobs failed or completed with errors for more information. To view job details, click the Actions button next to the transfer line and then click View details.

- Completed with Errors (with warning symbol icon)—indicates that the transfer has completed
 but encountered errors. The number of skipped files is displayed. You can skip failed files by clicking
 the Actions button next to the transfer line and then clicking Skip failed files. See Express Transfer reporting jobs failed or completed with errors for more information. To view job details, click the
 Actions button next to the transfer line and then click View details.
- Cancelled—indicates that the transfer has been cancelled from within RelativityOne Import/Export or
 from within the Express Transfer desktop application. To view more information about the job, click
 the Actions button next to the transfer line and then click View details.

To check the full history, visit the Import/Export Job page in RelativityOne. Refer to Import/Export Job tracking and history for more information.


6.9.0.4 Filtering Express Transfer jobs

To filter your jobs based on the type of transfer (Import or Export) on the In Progress or History tabs, click the drop-down arrow and select **Import** or **Export**. By default, all transfer types are displayed.




6.9.0.5 Viewing and copying details of Express Transfer jobs

To obtain information about a particular Express Transfer job, click the **Actions** button next to the transfer line and then click **View details**.



The Job details window displays the transfer information. Click the **copy button** and paste the information to the clipboard to use it elsewhere.

if you need to copy




6.10 Express Transfer reporting jobs failed or completed with errors

When using Express Transfer with Import/Export, if a job fails to finish or completes with errors, you can generate a report from Express Transfer Job Details. The report includes information such as the time stamp, file status, file name, error message, and file path. You also have a few options on how to handle the failed or errored jobs, such as retrying or skipping failed files. For more information about job tracking and history, see Express Transfer Job tracking and history on page 66.


Note: Available for Express Transfer version 2.21.1 and above. See <u>Locating the Express Transfer</u> version number on page 38 if needed.

- 1. From the Express Transfer application, click the **History** tab.
- 2. Click the **Actions** button corresponding with the job that failed or completed with warnings and do any of the following:



- View details—click to view job information in another window.
- Show report—click to view the saved Excel file (.csv) with the failed jobs or those completed with errors. This link will open File Explorer on your local drive to the Reports folder, such as C:\Users\<username>\AppData\Local\Express Transfer\Reports. You cannot generate a report for jobs that were run prior to upgrading to version 2.21.1.
- Retry failed files—click to rerun the failed files. Jobs older than seven days cannot be rerun.
- **Skip failed files**—click to continue running the job excluding the failed files. The job status will be "Completed with errors." The successful documents will be uploaded and available. You can view information about the failed files by clicking **Show report** to decide how you want to proceed with them. This option is recommended if you attempted to retry the failed files and the job still fails. Once Skip failed files is executed, the Retry failed files option is no longer avail-

able.



7 Importing data using Import/Export

You can use Import/Export to import unprocessed raw native files, document load files, image load files, production load files, and Relativity Dynamic Objects. Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

Note: After documents are imported using Import/Export, you can automate creating a dtSearch index or run a search terms report with those documents using Automated Workflows. To learn more, visit Automated Workflows.

- <u>Document load file import</u>—use this workflow to import load files containing document metadata, native files, or extracted text into Relativity.
- <u>Image load file import</u>—use this workflow to import load files containing images and PDFs into Relativity.
- Production load file import
 —use this workflow to import load files containing productions into Relativity.
- Relativity Dynamic Object load file import
 —use this workflow to import dynamic object (RDO) data into Relativity.
- Access DB load file import (MDB)—use this workflow to import an Access DB load file (MDB) into Relativity.
- <u>Unstructured data workflow with Processing</u>—use this workflow to import raw (unprocessed) native files that require processing in Relativity.
- <u>Transcript data import for Processing</u>—use this workflow to import transcript MDB data with the linked audio/video files into RelativityOne

7.1 Pre-check Load File

The Pre-check Load File is an optional process when configuring an import job. It ensures consistency of date before the import job starts.

This feature helps to identify data inconsistencies early, allowing you to correct the source load file for a successful import job. That way, you don't need to run the entire import job, including transferring native files and images, to detect potential load file errors. The Pre-check Load File process reduces time needed for complete load file imports using Import/Export, particularly for large load files.

The Pre-check load file process validates different data depending on the import workflow.

Note: The Pre-check Load File feature is not available in workflows that utilize Staging. If your import job is configured to use Staging, the Pre-check step will be skipped, and validation will occur during the actual import process.

7.1.1 Document and RDO load file import

For these workflows, the Pre-check Load File validations are based on the configured Fields Mapping. The load file metadata is compared with the mapped workspace fields. It is also checked if the metadata can be

successfully imported to the selected fields.


The Pre-check load file process validates the following:

- Date/Time format— checks if the metadata mapped to Data/Time fields is within acceptable format, expected by the Relativity field.
- Field type—checks if the metadata type matches the expected type of the selected field, for example Date/Time, Number, Text, Boolean.
- Field length—checks if the text metadata is not longer than maximum number of characters defined for the selected Relativity field.
- Number of the load file cells—checks if each row of the load file contains the same number of columns and if it matches the number of the mapped fields.
- Number of folders and choice fields—checks total number of folders and choice fields that will be created during the import job. Large total number may significantly extend the job processing time.
- File paths for native and extracted text files—checks if the file paths lead to actual files to be uploaded during the import job.

The Pre-check Load file process validates all load file rows against the metadata consistency. It also validates random 1,000 rows across the entire load file against the file paths errors. The file paths validation is run when using either Express Transfer or Web Upload for importing files.

After the validation, the summary dialog displays identified errors, which are divided into error categories. You can click the down arrow next to any error category to view its details.

The summary dialog displays a maximum of 1,000 errors for each error category, so your web browser responsiveness is not affected. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down list.




7.1.2 Image and Production load file import

For these workflows, the Pre-check Load File validates if image or PDF file paths lead to actual files which will be uploaded during the import job.

During that process, random 1,000 rows across the entire load file are checked against the file paths errors. The file paths validation is run when using either Express Transfer or Web Upload mode for importing files.

After the validation, the summary dialog displays identified errors, which are divided into error categories. You can click the down arrow next to any error category to view its details.



7.1.3 Working with Pre-check Load File results

When the Load File Pre-check process is complete, you may choose to correct the errors in the source files and upload the files again. To do so, keep clicking back to the Choose Load File And Location dialog. Then, upload the corrected files and perform the import steps again.

If you don't want to correct the source files, click the **Import** button and proceed with importing the data.

7.2 Importing data using Import/Export

You can use Import/Export to import unprocessed raw native files, document load files, image load files, production load files, and Relativity Dynamic Objects. Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

Note: After documents are imported using Import/Export, you can automate creating a dtSearch index or run a search terms report with those documents using Automated Workflows. To learn more, visit Automated Workflows.

• <u>Document load file import</u>—use this workflow to import load files containing document metadata, native files, or extracted text into Relativity.

- <u>Image load file import</u>—use this workflow to import load files containing images and PDFs into Relativity.
- <u>Production load file import</u>—use this workflow to import load files containing productions into Relativity.
- Relativity Dynamic Object load file import—use this workflow to import dynamic object (RDO) data into Relativity.
- Access DB load file import (MDB)—use this workflow to import an Access DB load file (MDB) into Relativity.
- <u>Unstructured data workflow with Processing</u>—use this workflow to import raw (unprocessed) native files that require processing in Relativity.
- <u>Transcript data import for Processing</u>—use this workflow to import transcript MDB data with the linked audio/video files into RelativityOne

7.2.1 Pre-check Load File

The Pre-check Load File is an optional process when configuring an import job. It ensures consistency of date before the import job starts.

This feature helps to identify data inconsistencies early, allowing you to correct the source load file for a successful import job. That way, you don't need to run the entire import job, including transferring native files and images, to detect potential load file errors. The Pre-check Load File process reduces time needed for complete load file imports using Import/Export, particularly for large load files.

The Pre-check load file process validates different data depending on the import workflow.

Note: The Pre-check Load File feature is not available in workflows that utilize Staging. If your import job is configured to use Staging, the Pre-check step will be skipped, and validation will occur during the actual import process.

7.2.1.1 Document and RDO load file import

For these workflows, the Pre-check Load File validations are based on the configured Fields Mapping. The load file metadata is compared with the mapped workspace fields. It is also checked if the metadata can be successfully imported to the selected fields.

The Pre-check load file process validates the following:


- Date/Time format— checks if the metadata mapped to Data/Time fields is within acceptable format, expected by the Relativity field.
- Field type—checks if the metadata type matches the expected type of the selected field, for example Date/Time, Number, Text, Boolean.
- Field length—checks if the text metadata is not longer than maximum number of characters defined for the selected Relativity field.
- Number of the load file cells—checks if each row of the load file contains the same number of columns and if it matches the number of the mapped fields.
- Number of folders and choice fields—checks total number of folders and choice fields that will be created during the import job. Large total number may significantly extend the job processing time.

• File paths for native and extracted text files—checks if the file paths lead to actual files to be uploaded during the import job.

The Pre-check Load file process validates all load file rows against the metadata consistency. It also validates random 1,000 rows across the entire load file against the file paths errors. The file paths validation is run when using either Express Transfer or Web Upload for importing files.

After the validation, the summary dialog displays identified errors, which are divided into error categories. You can click the down arrow next to any error category to view its details.

The summary dialog displays a maximum of 1,000 errors for each error category, so your web browser responsiveness is not affected. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down list.




7.2.1.2 Image and Production load file import

For these workflows, the Pre-check Load File validates if image or PDF file paths lead to actual files which will be uploaded during the import job.

During that process, random 1,000 rows across the entire load file are checked against the file paths errors. The file paths validation is run when using either Express Transfer or Web Upload mode for importing files.

After the validation, the summary dialog displays identified errors, which are divided into error categories. You can click the down arrow next to any error category to view its details.



7.2.1.3 Working with Pre-check Load File results

When the Load File Pre-check process is complete, you may choose to correct the errors in the source files and upload the files again. To do so, keep clicking back to the Choose Load File And Location dialog. Then, upload the corrected files and perform the import steps again.

If you don't want to correct the source files, click the **Import** button and proceed with importing the data.

7.3 Importing a document load file

You can use Import/Export to import document load files, .dat, .csv, and .txt, into RelativityOne that contain document metadata, native files, or extracted text. You're also able to use saved job profiles to expedite the configuration process.


If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.

Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To import a document load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Structured** (**Processed**) **Data** workflow box to import a document load file to your workspace.

Import/Export



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See <u>Activating and deactivating Express Transfer on page 44</u> for more information.

4. On the Choose the Load File Type dialog, click the **Document** box to import a document load file to your workspace.




- 5. If Express Transfer is not Active, skip this step. If it is Active:
 - Click **Select Folder**on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath.
 - Click Staging Load File to select a load file from the StructuredData folder in Staging.

Notes:

- Accessing Choose from Staging requires Allow Staging Import permissions. Refer to the <u>Permissions on page 13</u> page for more information.
- If you choose to import load file data from Staging, the load file and all linked files will be copied to the destination located outside of your Staging Area. After the import is completed, you can clean up the source data in Staging.


Import/Export



Notes:

- You can choose only one folder with a load file to transfer.
- File names must be 200 characters or less, including the extension.
- We recommend using a local drive instead of a mapped or external drive to avoid potential slowness and connection issues with the file import process. Also see <u>Data transfer per-</u> formance considerations on page 47.
- · When Express Transfer is active, you should not zip data for importing.
- When Express Transfer is active, it uploads only files linked in the selected load file, regardless of their location.
- When Express Transfer is active, it ignores mismatches in upper and lower case between file paths in the load file and the actual file names.
- When Express Transfer is active, it supports load files with relative paths, absolute paths, and UNC paths. It is possible to mix different path types in a single load file.
- 6. On the Choose Load File and Location dialog, complete the following fields, then click **Continue**. Refer to Import/Export load file specifications for more information regarding load files.

Import/Export



- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job Page. The Job name field accepts up to 50 characters.
- **Destination folder**—click the **Select** button, and do one of the following:
 - Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click Create, enter
 a new folder name, click out of the new folder to save it, then click Select.
- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example. Profiles with the ".ie" extension can only be used in Import/Export.
 - None—select this option if you do not desire to use a profile for this import or if you
 intend to create a new profile based on the settings entered in the upcoming steps. You

will be able to save the profile settings later to an .ie file via the **Download Profile (.ie)** button.

- From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile, created via the former Relativity Desktop Client
 application, to reuse the job settings for this workflow. Use the drag and drop feature or
 browse for a file to choose it. All job settings provided within the selected profile file will
 be automatically entered where applicable in the succeeding workflow dialogs.
- Regional Settings (Date and Time)—select the desired format for imported date and time
 data. A preview of the chosen format will appear below the selection. The setting selected will
 remain for all future jobs until you choose another one from the list or until you clear your
 browser cache. When browser cache is cleared, the setting will revert to the US date and time
 by default.
- Load File—use the drag and drop feature or click browse for a file to select the document load file from your local drive.
- **Choose From Staging**—select a load file from the StructuredData in Staging. Your load file data must not be zipped. Otherwise, you will not be able to choose it from Staging.
- Include Native & Text—select this option to include native and text files.


Note: The Include Native & Text option is not available for <u>image</u> or <u>production</u> import workflows as there are no native files included in OPT files.

- Native & Text—if Include Native & Text was selected, use the drag and drop feature or click browse for a file to select the zipped native and text file from your local drive. See <u>ZIP archive</u> with extracted text and natives on page 22.
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- On the Load File Settings dialog, select the delimiters and encoding values of the document load file
 for the import, then click **Continue**. The File Column Headers Preview pane will help you to choose
 the proper settings.



• File Encoding—select an encoding format for the document load file. Consult your processing vendor or department to determine the correct encoding option, if necessary. The File Column Headers Preview pane automatically updates when you select the File Encoding type. Since the load file is parsed based on the delimiter set, you may need to check delimiters used in the load file if the column headers are not lined up correctly. Determine the delimiters used in the file, and then select them in the delimiters section of this dialog.

- First Line Contains Column Names toggle—select this option if the first line contains column names. Select the delimiters and encoding values used by your load file as needed:
 - Column—select the character used to separate columns.
 - Quote—select the character used as the text qualifier.
 - **Newline (Long Text Fields)**—select the character used to indicate the end of a line in any extracted text or long text field.
 - Multi-Value—select the character used to separate choices within a field.
 - Nested Value—select the character used to separate the different levels of a multichoice hierarchy.
- 8. On the Load File Fields Mapping dialog, select the load file fields to import and map them to the workspace fields, then click **Continue**.




- Click Auto Map Fields to automatically map fields. The fields from the load file will be mapped
 to any existing fields of the exact same name in the workspace. Any fields without a match will
 display "Choose..." in the Workspace Fields column. You will need to select one from the dropdown list. To search for a field in the list, begin typing the desired field name and matching
 search results are displayed for selection.
- · Consider the following when auto-mapping fields:
 - Case is not taken into account for the mapping. For example, a field named "email" in the load file would map to a field named "Email" in the workspace.
 - Spacing is taken into account. For example, in a two-word field name, if there is one space between words in the workspace field, and two spaces between words in the load file field, the fields will not be mapped.
 - Characters are mapped only to themselves. For example, an underscore is only mapped to another underscore, not to a space.

- Only fields matched or those with additional settings selected are loaded into the workspace.
 Other fields in the Load File Fields and Workspace Fields are ignored. You must always match the identifier field for the load file.
- When field names in the load file don't match precisely field names in the workspace, you can click **Map with Al** to map similarly named fields.
- Consider the following when mapping fields with AI:
 - Your data is neither used for training nor sent outside of the RelativityOne infrastructure. It remains fully protected within our secure environment.
 - Fields are mapped based on the similarities in the meaning of fields' names.
 - Fields are mapped automatically when the name meaning similarities are strong.
 - The **Review** label appears for the mappings that may require your attention.
 - Fields remain unmapped if the AI model cannot understand the meaning of the field name, or the name similarities are below the threshold. If you want to map these fields, choose a corresponding field from the Workspace Fields list or create a new workspace field.
- 9. Depending on your workflow, complete the following additional fields on this dialog:
 - **Sort by** button—click to choose your preferred sorting option:
 - Default (A-Z)—sorts all rows in alphabetical order, based on the load file field names.
 - Mapped on top—brings the mapped fields to the top and sorts them in alphabetical order.
 - **Unmapped on top**—brings the unmapped fields to the top and sorts them in alphabetical order.
 - **Review on top**—brings the mapped fields which require review to the top and sorts them in alphabetical order.
 - Create Field button—click if you want to create a new workspace field.
 - Export to CSV button—click to save the field mapping configuration to a .csv file on your local drive. This option cannot be accessed after the job has run and can only be selected prior to executing the job.
 - Load File Sample column—presents read-only example data from the load file fields.
 - Load File Fields column—displays the field names from the load file. Use the Filter box to search for field names.
 - **Workspace Fields** column—allows you to manually map the load file fields to the existing workspace fields. Use the Filter box to search for field names.
 - Additional Field Settings column—to enable additional field settings, click the Choose down arrow in this column to select the additional field as follows:
 - Text File—select this option if the mapped Long Text field contains a relative path, absolute path, or UNC path to a text file, and then select the File Encoding type for the file. If using absolute or UNC paths, Express Transfer must be activated prior to starting the import job. This field was renamed from Extracted Text since it now applies to any Long

Text field.

- **Folder Information Column**—select this option if you want to use a metadata field to build the folder structure for the workspace.
- Native File—select this option if the field from your load file contains a relative path, absolute path, or UNC path to the native files. If using absolute or UNC paths, Express Transfer must be activated prior to starting the import job.
- On the Import Settings dialog, configure your import job by selecting from which line number you want the load file to begin importing and how you want the records to be imported.



- **Start Line**—select the line number in the load file where you want the import process to begin. The default value is set to 0, which results in loading the entire load file.
- Import mode—choose an import mode:
 - Append Only—loads only new records.
 - Overlay Only—updates existing records only. If selected, then you must include an
 Overlay Identifier in an overlay load. This field acts as a link indicating to RelativityOne
 where to import the data.
 - Append/Overlay—adds new records and overlays data on existing records.

Note: For Append/Overlay and Overlay Only, if a blank metadata field exists in the load file, .dat or.csv, the blank value will overlay (remove) any existing value that may reside in the corresponding mapped field.

- Multi-Select Field Overly Behavior—this field appears if you selected Overlay Only or Append/Overlay as the Import Mode and have mapped at least one Multiple Choice or Multiple Object field. Choose one of the following options:
 - Use Field Settings—merges or replaces all values for multi-choice and multi-object
 fields in the load file with corresponding multi-choice and multi-option fields in the workspace. The fields are merged according to the overlay behavior settings in the environment.
 - Merge Values—merges all values for multi-choice and multi-object fields in the load file
 with corresponding multi-choice and multi-option fields in the workspace. The fields are
 merged regardless of the overlay behavior settings in the environment.
 - **Replace Values**—replaces all values for multi-choice and multi-object fields in the load file with corresponding multi-choice and multi-option fields in the workspace. The fields are merged regardless of the overlay behavior settings in the environment.


- 11. (Optional) Click **Download Profile (.ie)** on the Import Settings dialog to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.
- 12. (Optional) Click **Precheck Load File** on the Import Settings dialog to run a validation process on the load file to check for errors prior to importing it.


Note: If the workflow is configured to use Staging, the Pre-check Load File step will be unavailable. Ensure your load file is validated manually before proceeding.

All detected errors are displayed in the Pre-check window. Click the down arrow next to any error message to view its details. If you want to correct the errors in the source file(s) and repeat the importing steps, click **Cancel**to discontinue importing the file at this time. Otherwise, go to the next step to import the load file with errors and correct them later. The following validations are performed during precheck:

- · Date format
- · Field type
- · Field length
- · Number of load file cells
- · Number of folders and choice fields
- File paths for natives and extracted text. The precheck checks 1,000 random lines across the whole load file.

Note: The Pre-check Load File summary dialog displays a maximum of 1,000 errors for each error category. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down list.









- 13. Click the **Import** button to start the importing process.
- 14. Review the importing progress on the **Overview** tab on the Importing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. If needed, click **Cancel** to stop the import job before it completes. Otherwise, click **Close** when the importing process is complete.

Caution: If you used Import/Export in web only mode, meaning Express Transfer was not active, do **not** close the Importing dialog until *after* the Uploading step has successfully completed. Closing the dialog prior to the Uploading step completing will terminate the data transfer (upload) process.



15. Go to the **Job Settings** tab on the Importing dialog to review the job configuration settings. If desired, click **Download Profile** (.ie) to download the job configuration settings entered thus far to an .ie file

on your computer. This way they can be reused for other jobs.




16. If no errors were found in the load file, go to the next step. If errors were found, click the **Errors** tab on the Importing dialog to view them, then do either of the following:

Note: Only records that imported without errors will appear in the workspace.

- To proceed without correcting the errors, click Close.
- To manually correct them now, click the **Download Error Load File** button. Review the errors
 and correct them as needed. When you have finished, upload the file with the corrected data
 by clicking the **Select** button on the Importing screen next to New Load File. Then, navigate to
 the load file on your local drive to select it. Once selected, click **Import** to import the job with
 corrected data.

Note: You can only correct documents included in the original load file. If you need to add missing documents, create a new import job.



17. Click **Finish** to close the dialog.

You can review the Import/Export Job page to see more information about the job. Refer to Import/Export Job tracking and history for details.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see Express Transfer Job tracking and history. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.4 Importing an image load file

You can use Import/Export to import image and PDF load files that are Opticon-formatted (.opt) page-level files. When you import images, they are added to a workspace as documents. When you import PDFs, they are visible in the PDF Viewer and Extracted Text view, if you included text files. To import PDFs as images, they must be converted to an image file type, .tiff or .jpg, before you run the import job.

See Community articles <u>How to import multipage PDF files with Express Transfer Active</u> and <u>How to import multipage PDF files using Import/Export for more information.</u>

RelativityOne only accepts the following types of files:

- Single page TIFF (Group IV)
- · Single page JPG
- Single and multiple PDF; files must have a .pdf extension

Note: Import/Export expects all the files in the OPT load files to be of the same type. This means you cannot mix image and PDF files in the same load file.


If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.

Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To import an image load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Structured** (**Processed**) **Data** workflow box to import an image load file to your workspace.

Import/Export



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Choose the Load File Type dialog, click the **Image** box to import an image load file to your workspace.




- 5. If Express Transfer is not Active, skip this step. If it is Active:
 - Click **Select Folder**on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath.
 - Click Staging Load File to select a load file from the StructuredData folder in Staging.

Notes:

- Accessing Choose from Staging requires Allow Staging Import permissions. Refer to the <u>Permissions</u> page for more information.
- If you choose to import load file data from Staging, the load file and all linked files will
 be copied to the destination located outside of your Staging Area. After the import is
 completed, you can clean up the source data in Staging.


Import/Export



Notes:

- · You can choose only one folder with a load file to transfer.
- File names must be 200 characters or less, including the extension.
- We recommend using a local drive instead of a mapped or external drive to avoid potential slowness and connection issues with the file import process. Also see <u>Data transfer per-</u> formance considerations on page 47.
- · When Express Transfer is active, you should not zip data for importing.
- When Express Transfer is active, it uploads only files linked in the selected load file, regardless of their location.
- When Express Transfer is active, it ignores mismatches in upper and lower case between file paths in the load file and the actual file names.
- When Express Transfer is active, it supports load files with relative paths, absolute paths, and UNC paths. It is possible to mix different path types in a single load file.
- 6. On the Choose Load File and Location dialog, complete the following fields, then click **Continue**. Refer to Import/Export load file specifications for more information regarding load files.


Import/Export



- **Job name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- **Destination folder**—click the **Select** button, and do one of the following:
 - Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click **Create**, enter a new folder name, click out of the new folder to save it, then click **Select**.
- **Profile**—the job configuration settings that were previously saved to a profile file (.ie or .kw*). They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example. Profiles with the ".ie" extension can only be used in Import/Export.
 - **None**—select this option if you do not desire to use a profile for this import or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later to an .ie file via the **Download Profile (.ie)** button.
 - From Local Disk Profiles—use this option to select a previously saved Import/Export profile (.ie file) or an existing .kw* profile, created via the former Relativity Desktop Client

application, to reuse the job settings for this workflow. Use the drag and drop feature or browse for a file to choose it. All job settings provided within the selected profile file will be automatically entered where applicable in the succeeding workflow dialogs.

- Load file—drag and drop or use browse for a file to select the load file from your local drive.
- **Choose From Staging**—select a load file from the StructuredData in Staging. Your load file data must not be zipped. Otherwise, you will not be able to choose it from Staging.
- **Images**—drag and drop or use **browse for a file** to select a zipped image file from your local drive. See Image and extracted text files on page 23.
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. On the Import Settings dialog, configure your import job by selecting the numbering and choosing the import mode.




- **Start Line**—select the line number in the load file where you want the import process to begin. The default value is set to 0, which results in loading the entire load file.
- Numbering—select one of the following options:
 - Use load file page IDs—default setting.
 - **Auto-number pages**—select this option if page IDs in the production are not unique. For example, you might import a set of .tiff files that share a page identifier for each record. The page identifiers are shared per document and are not unique. The Autonumber pages option appends the 01, 02, and so on to the page-level identifier, creating a unique number per page.
- Import Mode—choose how you want the records to be imported:
 - Append Only—load only new records.
 - Overlay Only—update existing records only. If selected, then you must assign a unique
 identifier in the Overlay Identifierfield that will be used to overlay data in the workspace. This field acts as a link indicating to RelativityOne where to import the data.
 - Append/Overlay—adds new records and overlays data on existing records.
- (Optional) Load Extracted Text toggle—select this option to load new text for Production documents that may be revised based on redactions. The Files encoding field will be displayed once this toggle is selected. The text files must be meet these requirements:

- · Have .txt extensions
- Stored in the same directory as image files
- · Named in the same way as the image files
- **Files encoding**—this field displays if the Load Extracted Text option is selected. Choose the encoding format for the text file:
 - Western European (Windows)—indicates the Windows standard encoding for English.
 - **Unicode**—utilizes more than 107,000 characters covering 90 scripts.
 - Unicode (Big-Endian)—is the same as Unicode, except that the byte order is reversed.
 - **Unicode (UTF-7)**—represents Unicode text using a stream of ASCII characters to guarantee that the high bit will always be zero.
 - Unicode (UTF-8)—represents all characters in the Unicode character set using 8-bit bytes.
- 8. (Optional) Click **Download Profile (.ie)** on the Import Settings dialog to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.
- 9. (Optional) Click **Precheck Load File** on the Import Settings dialog to run a validation process on the load file to check for errors prior to importing it.

Note: If the workflow is configured to use Staging, the Pre-check Load File step will be unavailable. Ensure your load file is validated manually before proceeding.


The following validation is performed during precheck: Image file paths. The precheck checks 1,000 random lines across the whole load file. All detected errors are displayed in the Pre-check window. Click the down arrow next to any error message to view its details. If you want to correct the errors in the source file(s) and repeat the importing steps, click **Cancel**to discontinue importing the file at this time. Otherwise, go to the next step to import the load file with errors and correct them later.

Note: The Pre-check Load File summary dialog displays a maximum of 1,000 errors for each error category. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down list.




- 10. Click the **Import** button to start the importing process.
- 11. Review the importing progress on the **Overview** tab on the Importing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. If needed, click **Cancel** to stop the import job before it completes. Otherwise, click **Close** when the importing process is complete.

Caution: If you used Import/Export in web only mode, meaning Express Transfer was not active, do **not** close the Importing dialog until *after* the Uploading step has successfully completed. Closing the dialog prior to the Uploading step completing will terminate the data transfer (upload) process.



12. Click the **Job Settings** tab on the Importing dialog to review the job configuration settings. If desired, click **Download Profile (.ie)** to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.




13. If no errors were found in the load file, go to the next step. If errors were found, click the **Errors** tab on the Importing dialog to view them, then do either of the following:

Note: Only records that imported without errors will appear in the workspace.

- To proceed without correcting the errors, click Close.
- To manually correct them now, click the **Download Error Load File** button. Review the errors and correct them as needed. When you have finished, upload the file with the corrected data

by clicking the **Select** button on the Importing screen next to New Load File. Then, navigate to the load file on your local drive to select it. Once selected, click **Import** to import the job with corrected data.

Note: You can only correct documents included in the original load file. If you need to add missing documents, create a new import job.



14. Click **Finish** to close the dialog.

You can review the Import/Export Job page to see more information about the job. Refer to Import/Export Job tracking and history for details.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see "Express Transfer Job tracking and history". You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.5 Importing a production load file

You can use Import/Export to import external productions, including single and multiple PDF files, into RelativityOne with Import/Export. This is useful after a production goes out the door in the event a case team needs access to documents as they were in the production and needs them available for searching.

If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.


Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To import a production load file:

Note: You can import data from a production load file into an existing production. If no production sets exist in the workspace, you must create one before starting an import job. For more details, refer to the Production documentation. If you want to import a production consisting of produced images, natives, and extracted text, see this Community article.


- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Structured** (**Processed**) **Data** workflow box to import a production load file into your workspace.

Import/Export



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Choose the Load File Type dialog, click the **Production** box to import a production load file to your workstation.




- 5. If Express Transfer is not Active, skip this step. If it is Active:
 - Click **Select Folder**on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath.
 - Click Staging Load File to select a load file from the StructuredData folder in Staging.

Notes:

- Accessing Choose from Staging requires Allow Staging Import permissions. Refer to the <u>Permissions</u> page for more information.
- If you choose to import load file data from Staging, the load file and all linked files will
 be copied to the destination located outside of your Staging Area. After the import is
 completed, you can clean up the source data in Staging.


Import/Export



Notes:

- · You can choose only one folder with a load file to transfer.
- File names must be 200 characters or less, including the extension.
- We recommend using a local drive instead of a mapped or external drive to avoid potential slowness and connection issues with the file import process. Also see <u>Data transfer per-</u> formance considerations on page 47.
- · When Express Transfer is active, you should not zip data for importing.
- When Express Transfer is active, it uploads only files linked in the selected load file, regardless of their location.
- When Express Transfer is active, it ignores mismatches in upper and lower case between file paths in the load file and the actual file names.
- When Express Transfer is active, it supports load files with relative paths, absolute paths, and UNC paths. It is possible to mix different path types in a single load file.
- 6. On the Choose Load File and Location dialog, complete the following fields, then click **Continue**. Refer to Import/Export load file specifications for more information regarding load files.


Import/Export



- **Job name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- **Destination folder**—click the **Select** button, and do one of the following:
 - Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click **Create**, enter a new folder name, click out of the new folder to save it, then click **Select**.
- **Profile**—the job configuration settings that were previously saved to a profile file (.ie or .kw*). They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example. Profiles with the ".ie" extension can only be used in Import/Export.
 - **None**—select this option if you do not desire to use a profile for this import or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later to an .ie file via the **Download Profile (.ie)** button.
 - From Local Disk Profiles—use this option to select a previously saved Import/Export profile (.ie file) or an existing .kw* profile, created via the former Relativity Desktop Client

application, to reuse the job settings for this workflow. Use the drag and drop feature or browse for a file to choose it. All job settings provided within the selected profile file will be automatically entered where applicable in the succeeding workflow dialogs.

- Load file—drag and drop or use browse for a file to select the load file from your local drive.
- Choose From Staging—select a load file from the StructuredData in Staging. Your load file
 data must not be zipped. Otherwise, you will not be able to choose it from Staging.
- **Images**—drag and drop or use **browse for a file** to select a zipped image file from your local drive. See Image and extracted text files on page 23.
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. On the Import Settings dialog, you can select the production to import and choose the numbering and import mode settings.



Production—select the Production set to import.

Note: You can import data from a production load file into an existing production. If no production sets exist in the workspace, you must create one before starting an import job. For more details, refer to the **Production** documentation.

- **Start Line**—select the line number in the load file where you want the import process to begin. The default value is set to 0, which results in loading the entire load file.
- Numbering—choose the numbering option:
 - Use load file page IDs—default setting.
 - Auto-number pages—select this option if page IDs in the production are not unique.
- Import mode—choose how you want the records to be imported:
 - Append Only—loads only new records.
 - Overlay Only—updates existing records only. If selected, then you must assign a unique identifier in the Overlay Identifierfield that will be used to overlay data in the workspace. This field acts as a link indicating to RelativityOne where to import the data.
 - Append/Overlay—adds new records and overlays data on existing records. If selected, then you must assign a unique identifier in the Overlay Identifierthat will be used to


overlay data in the workspace. This field acts as a link indicating to RelativityOne where to import the data.

- 8. If you selected Overlay Only or Append/Overlay in the previous step, select an **Overlay Identifier** to specify the field that links your overlay load file to the workspace.
 - **Merge Values**—merges all values for multi-choice and multi-object fields in the load file with corresponding multi-choice and multi-option fields in the workspace. The fields are merged regardless of the overlay behavior settings in the environment.
 - **Replace Values**—replaces all values for multi-choice and multi-object fields in the load file with corresponding multi-choice and multi-option fields in the workspace. The fields are merged regardless of the overlay behavior settings in the environment.
 - **Use Field Settings**—merges or replaces all values for multi-choice and multi-object fields in the load file with corresponding multi-choice and multi-option fields in the workspace. The fields are merged according to the overlay behavior settings in the environment.
- 9. (Optional) Click **Download Profile (.ie)** on the Import Settings dialog to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.
- 10. (Optional) Click **Precheck Load File** on the Import Settings dialog to run a validation process on the load file to check for errors prior to importing it.

Note: If the workflow is configured to use Staging, the Pre-check Load File step will be unavailable. Ensure your load file is validated manually before proceeding.


The following validation is performed during precheck: Image file paths. The precheck checks 1,000 random lines across the whole load file. All detected errors are displayed in the Pre-check window. Click the down arrow next to any error message to view its details. If you want to correct the errors in the source file(s) and repeat the importing steps, click **Cancel**to discontinue importing the file at this time. Otherwise, go to the next step to import the load file with errors and correct them later.

Note: The Pre-check Load File summary dialog displays a maximum of 1,000 errors for each error category. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down list.




- 11. Click the **Import** button to start the importing process.
- 12. Review the importing progress on the **Overview** tab on the Importing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. If needed, click **Cancel** to stop the import job before it completes. Otherwise, click **Close** when the importing process is complete.

Caution: If you used Import/Export in web only mode, meaning Express Transfer was not active, do **not** close the Importing dialog until *after* the Uploading step has successfully completed. Closing the dialog prior to the Uploading step completing will terminate the data transfer (upload) process.



13. Go to the **Job Settings** tab on the Importing dialog to review the job configuration settings. If desired, click **Download Profile (.ie)** to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.




14. If no errors were found in the load file, go to the next step. If errors were found, click the **Errors** tab on the Importing dialog to view them, then do either of the following:

Note: Only records that imported without errors will appear in the workspace.

- To proceed without correcting the errors, click Close.
- To manually correct them now, click the **Download Error Load File** button. Review the errors and correct them as needed. When you have finished, upload the file with the corrected data

by clicking the **Select** button on the Importing screen next to New Load File. Then, navigate to the load file on your local drive to select it. Once selected, click **Import** to import the job with corrected data.

Note: You can only correct documents included in the original load file. If you need to add missing documents, create a new import job.



15. Click **Finish** to close the dialog.

You can review the Import/Export Job page to see more information about the job. Refer to Import/Export Job tracking and history for details.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see "Express Transfer Job tracking and history". You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.6 Importing an RDO load file

You can import Relativity's dynamic objects (RDO) for use in Relativity applications. The workflow for RDO data import follows the same general guidelines as those for document load file imports.

If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.


Refer to Import/Export load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To import RDO data:

- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.


3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Structured** (**Processed**) **Data** workflow box to import an RDO load file to your workspace.

Import/Export



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Choose the Load File Type dialog, click the RDO box to import a load file to your workspace.




- 5. If Express Transfer is not Active, skip this step. If it is Active:
 - Click **Select Folder**on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath.
 - Click Staging Load File to select a load file from the StructuredData folder in Staging.

Notes:


- Accessing Choose from Staging requires Allow Staging Import permissions. Refer to the Permissions on page 13 page for more information.
- If you choose to import load file data from Staging, the load file and all linked files will be copied to the destination located outside of your Staging Area. After the import is completed, you can clean up the source data in Staging.

Import/Export



Notes:

- · You can choose only one folder with a load file to transfer.
- File names must be 200 characters or less, including the extension.
- We recommend using a local drive instead of a mapped or external drive to avoid potential slowness and connection issues with the file import process. Also see <u>Data transfer per-</u> formance considerations on page 47.
- When Express Transfer is active, you should not zip data for importing.
- When Express Transfer is active, it uploads only files linked in the selected load file, regardless of their location.
- When Express Transfer is active, it ignores mismatches in upper and lower case between file paths in the load file and the actual file names.
- When Express Transfer is active, it supports load files with relative paths, absolute paths, and UNC paths. It is possible to mix different path types in a single load file.
- 6. On the Choose Load File and Location dialog, complete the following fields, then click **Continue**. Refer to Import/Export load file specifications for more information regarding load files.



- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job Page. The Job name field accepts up to 50 characters.
- **Relativity Object Type**—select the Relativity object type from the drop-down list that you want to import data.
- **Profile**—the job configuration settings that were previously saved to a profile file (.ie or .kw*). They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example. Profiles with the ".ie" extension can only be used in Import/Export.
 - **None**—select this option if you do not desire to use a profile for this import or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later to an .ie file via the **Download Profile (.ie)** button.

- From Local Disk Profiles—use this option to select a previously saved Import/Export profile (.ie file) or an existing .kw* profile, created via the former Relativity Desktop Client application, to reuse the job settings for this workflow. Use the drag and drop feature or browse for a file to choose it. All job settings provided within the selected profile file will be automatically entered where applicable in the succeeding workflow dialogs.
- Regional Settings (Date and Time)—select the desired format for imported date and time
 data. A preview of the chosen format will appear below the selection. The setting selected will
 remain for all future jobs until you choose another one from the list or until you clear your
 browser cache. When browser cache is cleared, the setting will revert to the US date and time
 by default.
- Load File—use the drag and drop feature or click browse for a file to select load file with RDO data from your local drive.
- Choose From Staging—select a load file from the StructuredData in Staging. Your load file data must not be zipped. Otherwise, you will not be able to choose it from Staging.
- Include Native & Text—select this option to include native and text files.


Note: The Include Native & Text option is not available for <u>image</u> or <u>production</u> import workflows as there are no native files included in OPT files.

- Native & Text—if Include Native & Text was selected, use the drag and drop feature or click
 browse for a file to select the zipped native and text file from your local drive. See <u>ZIP archive</u>
 with extracted text and natives on page 22
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. On the Load File Settings dialog, select the delimiters and encoding values of the load file for the import, then click **Continue**. The File Column Headers Preview pane will help you to choose the proper settings.



- File Encoding—select an encoding format for the load file. Consult your processing vendor or
 department to determine the correct encoding option, if necessary.
 The File Column Headers Preview pane automatically updates when you select the File Encoding type. Since the load file is parsed based on the delimiter set, you may need to check delimiters used in the load file if the column headers are not lined up correctly. Determine the
 delimiters used in the file, and then select them in the delimiters section of this tab.
- First Line Contains Column Names toggle—select this option if the first line contains column names.

- Select the delimiters and encoding values used by your load file:
 - Column—select the character used to separate columns.
 - Quote—select the character used as the text qualifier.
 - **Newline (Long Text Fields)**—select the character used to indicate the end of a line in any extracted text or long text field.
 - Multi-Value—select the character used to separate choices within a field.
 - Nested Value—select the character used to separate the different levels of a multichoice hierarchy.
- 8. On the Load File Fields Mapping dialog, select the load file fields to import and map them to the workspace fields, then click **Continue**.



- Click Auto Map Fields to automatically map fields. The fields from the load file will be mapped
 to any existing fields of the exact same name in the workspace. Any fields without a match will
 display "Choose..." in the Workspace Fields column. You will need to select one from the dropdown list. To search for a field in the list, begin typing the desired field name and matching
 search results are displayed for selection.
- Consider the following when auto-mapping fields:
 - Case is not taken into account for the mapping. For example, a field named "email" in the load file would map to a field named "Email" in the workspace.
 - Spacing is taken into account. For example, in a two-word field name, if there is one space between words in the workspace field, and two spaces between words in the load file field, the fields will not be mapped.
 - Characters are mapped only to themselves. For example, an underscore is only mapped to another underscore, not to a space.

- Only fields matched or those with additional settings selected are loaded into the workspace.
 Other fields in the Load File Fields and Workspace Fields are ignored. You must always match the identifier field for the load file.
- To import RDO data into a workspace, you must map the RDO identifier, whether it be Name, Control Number, or another field. If you do not, the import mode options will be limited and you will be unable to proceed with the import.
- When field names in the load file don't match precisely field names in the workspace, you can click **Map with Al** to map similarly named fields.
- Consider the following when mapping fields with Al:
 - Your data is neither used for training nor sent outside of the RelativityOne infrastructure. It remains fully protected within our secure environment.
 - Fields are mapped based on the similarities in the meaning of fields' names.
 - Fields are mapped automatically when the name meaning similarities are strong.
 - The **Review** label appears for the mappings that may require your attention.
 - Fields remain unmapped if the AI model cannot understand the meaning of the field name, or the name similarities are below the threshold. If you want to map these fields, choose a corresponding field from the Workspace Fields list or create a new workspace field.
- 9. Depending on your workflow, complete the following additional fields on this dialog:
 - Sort by button—click to choose your preferred sorting option:
 - Default (A-Z)—sorts all rows in alphabetical order, based on the load file field names.
 - **Mapped on top**—brings the mapped fields to the top and sorts them in alphabetical order.
 - **Unmapped on top**—brings the unmapped fields to the top and sorts them in alphabetical order.
 - Review on top—brings the mapped fields which require review to the top and sorts them in alphabetical order.
 - Create Field button—click if you want to create a new workspace field.
 - Export to CSV button—click to save the field mapping configuration to a .csv file on your local drive. Be aware that this option cannot be accessed after the job has run and can only be selected prior to executing the job.
 - Load File Sample column—presents read-only example data from the load file fields.
 - Load File Fields column—displays the field names from the load file. Use the Filter box to search for field names.
 - Workspace Fields column—allows you to manually map the load file fields to the existing workspace fields. Use the Filter box to search for field names.
 - Additional Field Settings column—to enable additional field settings, click the Choose down arrow in this column to select the additional field as follows:

- Native File—select this option if the field from your load file contains a relative path, absolute path, or UNC path to the native files. If using absolute or UNC paths, Express Transfer must be activated prior to starting the import job.
- Parent Object—select this option if the RDO has a parent that is not of Workspace type.
- 10. On the Import Settings dialog, configure your import job by selecting from which line number you want the load file to begin importing and how you want the records to be imported.



- **Start Line**—select the line number in the load file where you want the import process to begin. The default value is set to 0, which results in loading the entire load file.
- Import mode—choose how you want the records to be imported.
 - Append Only—loads only new records.
 - Append/Overlay—adds new records and overlays data on existing records. If selected, then you must assign a unique identifier in the Overlay Identifierfield that will be used to overlay data in the workspace. This field acts as a link indicating to RelativityOne where to import the data. For Append/Overlay and Overlay Only, if a blank metadata field exists in the load file, .dat or .csv, the blank value will overlay (remove) any existing value that may reside in the corresponding mapped field.
 - Overlay Only—updates existing records only. If selected, then you must include an Overlay Identifier next.
 - Overlay Identifier—if either Overlay Only or Append/Overlay mode is selected, then assign the unique identifier that will be used to overlay data in the workspace. This field acts as a link indicating to RelativityOne where to import the data.
- (Optional) Click **Download Profile (.ie)** on the Import Settings dialog to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.
- 12. (Optional) Click **Precheck Load File** on the Import Settings dialog to run a validation process on the load file to check for errors prior to importing it.


Note: If the workflow is configured to use Staging, the Pre-check Load File step will be unavailable. Ensure your load file is validated manually before proceeding.

All detected errors are displayed in the Pre-check window. Click the down arrow next to any error message to view its details. If you want to correct the errors in the source file(s) and repeat the importing steps, click **Cancel**to discontinue importing the file at this time. Otherwise, go to the next

step to import the load file with errors and correct them later. The following validations occur during pre-check:

- Date format
- Field type
- · Field length
- · Number of load file cells
- · Number of folders and choice fields
- File paths for natives and extracted text (checks 1,000 random lines across the whole load file)


Note: The Pre-check Load File summary dialog displays a maximum of 1,000 errors for each error category. It will also display a message indicating the total number of errors found. For example, if an error category has 2,000 errors, only the first 1,000 will be displayed in the drop-down.






- 13. Click the **Import** button to start the importing process.
- 14. Review the importing progress on the **Overview** tab on the Importing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. If needed, click **Cancel** to stop the import job before it completes. Otherwise, click **Close** when the importing process is complete.

Note: If you used Import/Export in web only mode, meaning Express Transfer was not active, do **not** close the Importing dialog until *after* the Uploading step has successfully completed. Closing the dialog prior to the Uploading step completing will terminate the data transfer (upload) process.



15. Go to the **Job Settings** tab on the Importing dialog to review the job configuration settings. If desired, click **Download Profile (.ie)** to download the job configuration settings entered thus far to an .ie file on your computer. This way they can be reused for other jobs.




16. If no errors were found in the load file, go to the next step. If errors were found, click the **Errors** tab on the Importing dialog to view them, then do either of the following:

Note: Only records that imported without errors will appear in the workspace.

- To proceed without correcting the errors, click Close.
- To manually correct them now, click the **Download Error Load File** button. Review the errors
 and correct them as needed. When you have finished, upload the file with the corrected data
 by clicking the **Select** button on the Importing screen next to New Load File. Then, navigate to
 the load file on your local drive to select it. Once selected, click **Import** to import the job with
 corrected data.

Note: You can only correct documents included in the original load file. If you need to add missing documents, create a new import job.



17. Click Finish to close the dialog.

You can review the Import/Export Job page to see more information about the job. Refer to Import/Export Job tracking and history for details.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see Express Transfer Job tracking and history. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.7 Importing an Access DB load file (MDB)

Note: The import and export workflows with Access DB (MDB) are designed for and are currently available for the Asia-Pacific region. For information on the possibility of enabling this flow in your instance, please contact your Account Representative.

You can use Import/Export to import document load files, .mdb .and mdbacc, into RelativityOne that contain document metadata, native files, or extracted text. You're also able to use saved job profiles to expedite the configuration process.


If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.

Refer to Access DB (MDB) load file specifications and Data upload size limitation on page 9 for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To import an Access DB load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Structured** (**Processed**) **Data** workflow box to import a document load file to your workspace.

Import/Export




Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Choose the Load File Type dialog, click the **Access DB** box to import an MDB load file to your workspace.




5. If Express Transfer is not Active, skip this step. If it is Active, click **Select** on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\Server-Name\SharedResourceName\FilePath.




Notes:

- · You can choose only one folder with a load file to transfer.
- File names must be 200 characters or less, including the extension.
- We recommend using a local drive instead of a mapped or external drive to avoid potential slowness and connection issues with the file import process. Also see <u>Data transfer per-</u> formance considerations on page 47.
- · When Express Transfer is active, you should not zip data for importing.
- When Express Transfer is active, it ignores mismatches in upper and lower case between file paths in the load file and the actual file names.
- When Express Transfer is active, it supports load files with relative paths, absolute paths, and UNC paths. It is possible to mix different path types in a single load file.
- 6. On the Choose Load File and Location dialog, complete the following fields. Then click **Continue**. Refer to Access DB (MDB) load file specifications for more information regarding load files.




• **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job Name field accepts up to 50 characters.

- **Destination folder**—click the **Select** button, and do one of the following:
 - · Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click Create, enter
 a new folder name, click out of the new folder to save it, then click Select.
- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields. For example, profiles with the ".ie" extension can only be used in Import/Export.
 - None—select this option if you do not desire to use a profile for this import or if you
 intend to create a new profile based on the settings entered in the upcoming steps. You
 will be able to save the profile settings later to an .ie file via the Download Profile (.ie)
 button.
 - From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile, created via the former Relativity Desktop Client
 application, to reuse the job settings for this workflow. Use the drag and drop feature or
 browse for a file to choose it. All job settings provided within the selected profile file will
 be automatically entered where applicable in the succeeding workflow dialogs.
- Regional Settings (Date and Time)—select the desired format for imported date and time
 data. A preview of the chosen format will appear below the selection. The setting selected will
 remain for all future jobs until you choose another one from the list or until you clear your
 browser cache. When browser cache is cleared, the setting will revert to the US date and time
 by default.
- Load File—use the drag and drop feature or click browse for a file to select the .mdb or .ac-cdb load file from your local drive.
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. On the Import Data Settings dialog, select options referring to file types you want to import. The following options are available:




- Import PDF Files toggle—select this option to import PDF files.
- Import Native Files toggle—select this option to import Native files.
- Import Text Files toggle—select this option to import Text files.
 - Workspace Long Text Field—select a field from your Relativity workspace that you
 want to import to.
 - Text File Encoding—select an encoding format for Text files.
- 8. On the Load File Fields Mapping dialog, select the load file fields to import and map them to the workspace fields, then click **Continue**.



- Click Auto Map Fields to automatically map fields. The fields from the load file will be mapped
 to any existing fields of the exact same name in the workspace. Any fields without a match will
 display "Choose..." in the Workspace Fields column. You will need to select one from the dropdown list. To search for a field in the list, begin typing the desired field name and matching
 search results are displayed for selection.
- · Consider the following when auto-mapping fields:
 - Case is not taken into account for the mapping. For example, a field named "email" in the load file would map to a field named "Email" in the workspace.
 - Spacing is taken into account. For example, in a two-word field name, if there is one space between words in the workspace field, and two spaces between words in the load file field, the fields will not be mapped.
 - Characters are mapped only to themselves. For example, an underscore is only mapped to another underscore, not to a space.

- Only fields matched or those with additional settings selected are loaded into the workspace.
 Other fields in the Load File Fields and Workspace Fields are ignored. You must always match the identifier field for the load file.
- When field names in the load file don't match precisely field names in the workspace, you can click **Map with Al** to map similarly named fields.
- Consider the following when mapping fields with AI:
 - Your data is neither used for training nor sent outside of the RelativityOne infrastructure. It remains fully protected within our secure environment.
 - Fields are mapped based on the similarities in the meaning of fields' names.
 - Fields are mapped automatically when the name meaning similarities are strong.
 - The Review label appears for the mappings that may require your attention.
 - Fields remain unmapped if the AI model cannot understand the meaning of the field name, or the name similarities are below the threshold. If you want to map these fields, choose a corresponding field from the Workspace Fields list or create a new workspace field.
- 9. On the *Import Settings* dialog, configure your import job by selecting from which line number you want the load file to begin importing and how you want the records to be imported.




- **Production**—select the Production set to import.
- **Start Line**—select the line number in the load file where you want the import process to begin. The default value is set to 0, which results in loading the entire load file.

- Workspace Folder Structure—choose the workspace structure:
 - MDB Folder Sturcture—uses the information from the levels data from the Export table.
 - Flat Structure—includes all documents in a single folder without the folder structure.
- Import mode—choose an import mode:
 - Append Only—loads only new records.
 - Overlay Only—updates existing records only. If selected, then you must include an
 Overlay Identifier in an overlay load. This field acts as a link indicating to RelativityOne
 where to import the data.
 - Append/Overlay—adds new records and overlays data on existing records.


Note: For Append/Overlay and Overlay Only, if a blank metadata field exists in the load file, the blank value will overlay (remove) any existing value that may reside in the corresponding mapped field.

- (Optional) Click **Download Profile (.ie)** on the Import Settings dialog to download the job configuration settings entered thus far to an .ie file on your computer. That way they can be reused for other jobs.
- 11. Click the **Import** button to start the importing process.
- 12. Review the importing progress on the **Overview** tab on the Importing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. If needed, click **Cancel** to stop the import job before it completes. Otherwise, click **Close** when the importing process is complete.

Caution: If you used Import/Export in web only mode, meaning Express Transfer was not active, do **not** close the Importing dialog until *after* the Uploading step has successfully completed. Closing the dialog prior to the Uploading step completing will terminate the data transfer (upload) process.




13. Go to the **Job Settings** tab on the Importing dialog to review the job configuration settings. If desired, click **Download Profile (.ie)** to download the job configuration settings entered thus far to an .ie file on your computer. That way they can be reused for other jobs.



14. If no errors were found in the .mdb file, click **Close**. If errors were found, you can click the **Errors** tab on the Importing dialog to view them. Then, click **Close** to close the dialog.

Import/Export



- To proceed without correcting the errors, click Close.
- To manually correct them now, click the **Download Error Load File** button. Depending on error types, you can download:
 - **Document Error Load File (.dat)**—for errors related to documents and native files import.
 - Image/PDF Error Load File (.opt)—for errors related to Images/PDFs import.

Note: If you want to correct the documents or add missing documents, create a new import job.

You can review the Import/Export Job page to see more information about the job. Refer to Import/Export Job tracking and history for details.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see Express Transfer Job tracking and history. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.8 Importing transcript MDB data for Processing via Import/Export Limited General Availability

Note: This content refers to Preview, Advance Access or limited-availability functionality that may not be available in all Relativity environments.

Note: Effective August 20, 2024, Import/Export uploads raw (unprocessed) data to the ProcessingSource folder and triggers the Processing application. The ProcessingSource folder is included in your Staging threshold. To avoid additional storage costs, you may want to delete the uploaded raw (unprocessed) data from this folder once it is no longer needed.

You can use Import/Export to import transcript MDB data with the linked audio/video files into RelativityOne. This will automatically trigger a Processing job to extract metadata from the selected transcript MBD file, create documents and link them with audio/video content included in the dataset, in one operation. Once the transcript data is successfully imported into your workspace, you can use the <u>Relativity Transcripts</u> application to review the content.

7.8.1 Before you begin

The following applications should be installed in a workspace before you begin using Relativity Transcripts:

- Import/Export
- Processing
- Transcripts

If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.

To import transcript MDB data with linked audio/video files for Processing:

Notes:

- Prepare the transcript dataset for import with Import/Export by creating a single ZIP file that contains the transcript MDB file and all linked audio and video files. No ZIP size limits apply.
- All files, including the MDB file, should be located on the top level of the ZIP file structure. The audio and video files cannot be included in a nested container.



• Do not edit the MDB file, and do not change the video file names. Changing the file names can cause errors.




- Do not add any other container or loose files to the ZIP file. Otherwise, the import job may fail.
- If you need to process additional data, do it in a separate set.

7.8.2 Importing transcript MDB data


- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Raw (Unprocessed) and Transcript MDB data** workflow box.

Import/Export




Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Choose Unstructured Data Type dialog, click the **Transcript MDB data** workflow box.




- 5. Select the transcript data files to import as follows depending on the activation status of Express Transfer:
 - With Express Transfer Active: Click Select on the Select data to Import dialog to browse to your local drive and select the folder that includes only the zipped transcript data you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar in the dialog box to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath. You also have the option on the dialog to choose from file share by clicking Choose from File Share, selecting the import source folder that includes only the zipped transcript data, and clicking Select Folder. Once the folder has been selected, click Continue.


Note: When you select a folder to upload, ensure that it contains **only the zipped Transcript data**. Express Transfer will transfer all the data from the selected folder, including sub-folders, to the staging area, regardless of the specific job configuration. If the selected folder contains any other files than the zipped transcript data, the import job may fail.



• With Express Transfer not Active: On the Select file dialog, do one of the following below to upload a file. Transcript MDB file along with the linked audio/video files must be zipped when using the first two options mentioned below.



- Drag and drop the zipped transcript data file into the upload area.
- Click browse for a file to select a zipped transcript data from your local drive.
- Click **Choose From Staging** to upload files directly from the Staging Area, select the folder that contains the zipped transcript file and click **Select**.
- 6. On the Transcript Import and Processing dialog, complete the following fields:



• **Job name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.

 Processing Profile—select the desired Processing profile. The Processing profile must already exist in Relativity.

Note: Select the Processing profile with the Auto-Publish setting enabled to automatically publish the discovered documents.

- Destination folder—click the Select button, and do one of the following:
 - · Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click **Create**, enter a new folder name, click out of the new folder to save it, and then click **Select**.
- Deponent—assign the deponent manually or by adding a new deponent now, as described below:

Note: The Deponent drop-down list shows custodians available in the workspace. When you create a new deponent with the Add Deponent feature, it is stored in the Entity Object as a custodian.

- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. Click Run Job to start importing data.

Note: Import/Export will upload all the zipped transcript data to the staging area and create a new Processing job based on the provided job configuration. The Processing application will extract the uploaded zip file and process the attached MDB file with the audio/video files.

8. Review the importing progress on the Importing & Processing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. Do any of the following:

Note: Only records that imported without errors will appear in the workspace.



- Click Cancel to stop the importing process before it completes.
- Click **Close** when the importing process is complete.

Note: If you imported data without activating Express Transfer, you can close the dialog before the import process finishes without causing an interruption in data flow as long as it's closed *after* the Uploading step is completed. Closing the dialog earlier will terminate the data transfer (upload) process.

• Click **Go to Processing** when the Discovery step begins to go to the Processing Sets page of the Processing application.

Import/Export utilizes the Processing application to process extract transcript metadata from the MDB file, create documents, and link the attached audio/video files. Depending on the processing profile configuration, the following processing phases will be triggered:

- Discovery
- Discovery and publish, if the auto-publish option is enabled in your processing profile

Notes:

- We recommend using the Processing application directly to determine global dedupe order creating processing sets.
- The Inventory phase of processing is always skipped when you import unstructured data. If Inventory is needed, use Staging Explorer to import data into RelativityOne, and then run Processing directly.

Please refer to Processing in Relativity documentation for more information about using the Processing application to ingest raw data directly into your workspace.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running, if desired, and the transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see "Express Transfer Job tracking and history". You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.9 Importing raw unprocessed data for Processing via Import/Export

Note: Effective August 20, 2024, Import/Export uploads raw (unprocessed) data to the ProcessingSource folder and triggers the Processing application. The ProcessingSource folder is included in your Staging threshold. To avoid additional storage costs, you may want to delete the uploaded raw (unprocessed) data from this folder once it is no longer needed.

You can use Import/Export to import native, unprocessed/unstructured files, including Slack data, into RelativityOne that require processing and it will automatically trigger a Processing job in one operation.

Notes:


- Import/Export is not a replacement for the Processing application; however it is a simplified workflow when setting up a processing set. Using the Processing application is recommended when setting up large, complex processing jobs. Also, within the Processing application, you can use Quick Create Sets, Inventory, check and update Processing Profiles, and customize data source options.
- Processing profiles must already exist in RelativityOne before using them in the steps below.
- For optimal performance, we recommend using Import/Export with Express Transfer and organizing data in such a way that there are as few Data Sources as possible in a single job.

If you want to use Import/Export with Express Transfer active, which is the recommended workflow for data transfer, refer to Express Transfer overview on page 32 for more information.

To import raw unprocessed/unstructured files for Processing:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, the **Import** button is selected by default. Next, click the **Raw (Unprocessed) and Transcript MDB data** workflow box to import native (raw) files into your workspace.

Import/Export



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.


4. On the Choose Unstructured Data Type, click the **Raw Data** workflow box.




- 5. Select the data files to import as follows depending on the activation status of Express Transfer:
 - With Express Transfer Active: Click Select on the Select data to Import dialog to browse to your local drive and select the folder with the files that you want to upload. In the case of universal naming convention (UNC) paths, you can copy and paste the path into the Select Folder address bar at the top of the dialog box in order to access the desired folder. For example, \\ServerName\SharedResourceName\FilePath.

You also have the option on the dialog to choose from file share by clicking **Choose from File Share**, selecting the import source folder, and clicking **Select Folder**. Once the folder has been selected, click **Continue**.

Note: When you select a folder to upload, Express Transfer will transfer **all** the data from the selected folder, including sub-folders, to the staging area, regardless of the specific job configuration, like the custodian mapping settings. This also applies to the load file import workflows.




• With Express Transfer not Active: On the Select file dialog, do one of the following below to upload a file. Data files must be zipped when using the first two options mentioned below. Single PST files do not require zipping.



- Drag and drop the zipped data file or single PST file into the upload area.
- Click browse for a file to select a zipped data or single PST file from your local drive.
- Click Choose From Staging to upload files directly from the Staging Area. Then, select
 the correct ProcessingSource folder and click Select. You do not need to zip files when
 importing with this option.

Note: Effective July 5, 2025, accessing Choose from Staging requires Allow Staging Import permissions. Refer to the Community article Changes to Import/Export Choose From Staging Option FAQ and the <u>Permissions on page 13</u> page for more information.

6. On the Create Processing Job dialog, complete the following fields:



- **Job name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- **Profile**—select the desired Processing profile. The Processing profile must already exist in Relativity.

Note: If you are importing Slack data, please refer to <u>Importing Slack short message data for Processing via Import/Export on page 146 below.</u>

- Destination folder—click the Select button, and do one of the following:
 - Choose an existing folder.
 - Create a new workspace folder by right-clicking on an existing folder, click **Create**, enter a new folder name, click out of the new folder to save it, and then click **Select**.
- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 7. Next, use the Select Data Sources section to select the **Data Sources** and assign **Custodians**. A maximum of 70 data sources (folders with data, loose files) can be selected and assigned custodians. See recommendations below for preparing data sources.


Notes:

Recommendations for preparing data sources.

- Each selected file is treated as a separate data source. Consider organizing loose files into folders per custodian.
- If you import data for a single custodian, you may want to create a top-level folder and place all the data into that folder to speed up the configuration and execution of the Processing job.
- To exclude Microsoft Office temporary files, which are those file names starting with a ~
 (tilde) sign, see <u>Exclude temporary Microsoft Office files from data import on page 57</u> for more information.
- Be sure your data sources have unique names. Data sources are **not** case sensitive. If you have data sources with duplicate names, you may see processing errors. For example, \\ [file.share]\Processing Source[SOURCE.NAME] and \\[file.share]\Processing Source[Source.Name] would be considered duplicate names since the system does not differentiate between capital and lower case letters. To make them unique, you could rename the folders [SOURCE.NAME1] and [Source.Name2].

Choose the **Data Source**by selecting the checkbox next to the folder name. Then, assign the **Custodian**manually or automatically, or by adding a new custodian now, as described below:

- **Manually assign custodians:** Select the proper custodian from the **Custodian** drop-down list and click the **Assign** button.
- Automatically assign custodians: Click the Auto Map Custodians button to automatically
 assign custodians to data source folders and files based on the naming pattern. Only the Last
 name, First name naming pattern is supported at this time. If you want to modify the automatic
 assignment, click Clear next to the custodian's name. The application reads data source
 names and checks if matching custodians have already been added to the Entity object.
 Depending on the result, one of the following occurs:
 - Custodian(s) already exists in the Entity: If the custodian(s) already exists in the
 Entity, the application automatically assigns corresponding custodians to folders and
 files.
 - New custodian automatically created: If the application cannot find the corresponding custodian in the Entity object, it creates a new one based on the data source name. Newly created custodians are marked with a blue dot in the Select Data Sources pane. New custodians will be added to the Entity object after you click Run Job in the next step. However, if you click Cancel instead of running the job, the new custodians will not be created.
- Add a new custodian now: If you want to add a new custodian to the drop-down list from here instead of through the Entity object, click the Add Custodian link, and do the following on the Add Custodian dialog:



- a. Select the custodian Type:
 - **Person**—select this option to enter a First Name and Last Name of the individual acting as custodian of the data to be processed.
 - Other—select this option if the custodian of the data to be processed is not an
 individual but is, for example, an entity or company name. Then, enter the name
 in the Full Name field. You can also select this option if you wish to enter an individual's full name without having that name include a comma once you export the
 data associated with it.
- b. Click the **Add Custodian** button. The newly created custodian will be added to the Custodian drop-down list. Then, you can select and assign the custodian to the data source.
- 8. Click **Run Job** to start importing data.

Note: Import/Export will upload all the zipped data to the Staging area, extract it, and create a new Processing job based on the data source selection. Only data sources assigned to custodians will be processed and imported to your workspace.

Note: Effective August 20, 2024, Import/Export uploads raw (unprocessed) data to the ProcessingSource folder and triggers the Processing application. The ProcessingSource folder is included in your Staging threshold. To avoid additional storage costs, you may want to delete the uploaded raw (unprocessed) data from this folder once it is no longer needed.

9. Review the importing progress on the Importing & Processing dialog. Real-time details regarding the number of transferred files and data size being processed are displayed during the Uploading and Extracting steps. Do any of the following:

Note: Only records that imported without errors will appear in the workspace.



- Click Cancel to stop the importing process before it completes.
- Click **Close** when the importing process is complete.

Caution: If you imported data without activating Express Transfer, you can close the dialog before the import process finishes without causing an interruption in data flow as long as it's closed *after* the Uploading step is completed. Closing the dialog earlier will terminate the data transfer (upload) process.

• Click **Go to Processing** when the Discovery step begins to go to the Processing Sets page of the Processing application.

Import/Export utilizes the Processing application to process native files, extract metadata, and create documents. Depending on the processing profile configuration, the following processing phases will be triggered:

- Discovery
- · Discovery and publish. If the auto-publish option is enabled in your processing profile

Notes:

- We recommend using the Processing application directly to determine global dedupe order creating processing sets.
- The Inventory phase of processing is always skipped when you import unstructured data. If Inventory is needed, use Staging Explorer to import data into RelativityOne, and then run Processing directly.

Please refer to Processing in Relativity documentation for more information about using the Processing application to ingest raw data directly into your workspace.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

Note: If you ran the job with Express Transfer active, you are able to close the Import/Export application while the job is running. The transfer job will continue and not be affected. You can monitor the progress and history of jobs within Express Transfer. For more information, see Express Transfer Job tracking and history. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

7.9.0.1 Importing Slack short message data for Processing via Import/Export

All commercial customers can now leverage Import/Export to upload Slack data for Processing.

To import Slack short messages for Processing via Import/Export:

- 1. Copy the zip file containing the Slack data into a folder on your drive.
- 2. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 3. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 4. Activate **Express Transfer**. See Activating and deactivating Express Transfer on page 44 for more information.

Note: If your organization is not permitted to use Express Transfer and you need to leverage the web mode of Import/Export to import Slack data, you must zip the folder in which the zip file is located from Step 1. Be aware that this will create an additional zip level, the zip file from Step 1 within a zipped folder file, for transport purposes only. For this reason, we recommend using Express Transfer for all your imports and exports.

- 5. On the Choose workflow dialog, the **Import** button is selected by default.
- 6. Click the Raw (Unprocessed) Data workflow box.
- 7. Provide the Job Name, select a Destination Folder, and select the Processing Profile.

Note: The following settings must already be enabled in the Processing Profile: **Convert Slack to RSMF** and **Download Attachments**. See Processing profiles documentation for more information.

- 8. For **Data Source**, select the folder that contains the zipped Slack data, then assign a **Custodian**.
- 9. Click **Run Job**. Import/Export uploads the data and passes the job configuration to the Processing application. Please refer to Processing in Relativity documentation for more information about using Processing to ingest raw data directly into your workspace.

Note: All the RSMF conversion is done in Processing automatically. See Processing documentation on RSMF files for more information.

8 Exporting data using Import/Export

You can use Import/Export to export the following:

- Exporting a folder—use this workflow to export a folder.
- Exporting a production set—use this workflow to export a production set.
- Exporting a saved search—use this workflow to export a saved search load file.
- Exporting RDO data—use this workflow to export Relativity's dynamic objects (RDO) load file.
- Exporting a saved search or a folder with Access DB load file (MDB)—use this workflow to export a
 saved search or a folder with Access DB load file (MDB).
- Exporting a production set with Access DB load file (MDB)—use this workflow to export a production set with Access DB load file (MDB).

Also see General recommendations for structured data import and export jobs on page 29.

8.1 Exporting data using Import/Export

You can use Import/Export to export the following:

- Exporting a folder—use this workflow to export a folder.
- Exporting a production set—use this workflow to export a production set.
- Exporting a saved search—use this workflow to export a saved search load file.
- Exporting RDO data—use this workflow to export Relativity's dynamic objects (RDO) load file.
- Exporting a saved search or a folder with Access DB load file (MDB)—use this workflow to export a saved search or a folder with Access DB load file (MDB).
- Exporting a production set with Access DB load file (MDB)—use this workflow to export a production set with Access DB load file (MDB).

Also see General recommendations for structured data import and export jobs on page 29.

8.2 Exporting a folder load file

You can use Import/Export to export folders and sub-folders out of RelativityOne.

If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.


Refer to Import/Export load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To export folders:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.

Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

3. On the Choose workflow dialog, click the **Export** button, then click **Folder**.



4. On the Export Settings, complete the following fields and click **Continue**:



Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- Folders—choose which workspace folder to export.
- **Export Sub-folders** toggle—select this option to export sub-folders of the previously selected folder.
- Views—select the workspace view that you would like to use to export metadata.

- **Profile**—the job configuration settings that were previously saved to a profile file (.ie or .kw*). They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - None—select this option if you do not desire to use a profile for this export or if you
 intend to create a new profile based on the settings entered in the upcoming steps. You
 will be able to save the profile settings later on the Export Job Configuration Summary
 dialog. The file extension for the new profile created will be ".ie".
 - From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use
 the drag and drop feature or browse for a file to choose it. All job settings provided within
 the selected profile file will be automatically entered where applicable in the succeeding
 workflow dialogs.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.


- Staging Area—select this option to create a copy of the data in the StructuredData folder in the Staging Area. You will need to use Staging Explorer later to download data. The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected data in the StructuredData folder in the Staging Area, as well as download it to your local disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths.
 You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:

 (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled. 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.



- Data File Format—select one of the formats below for the load file you are exporting:
 - .dat (Concordance)—load file exports with the standard Concordance delimiters.
 - .csv (Comma separated)—load file exports with comma separated delimiters.
 - .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
 - .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed when this option is selected.



• **Start Line**—select a line (record number) that identifies the initial document for export. The application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.


- Data File Encoding—select the encoding type for the document-level load file from the dropdown
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to include seconds with the exported date and time information. For example, the time will export as 12:10 AM (HH:MM AM/PM) when the toggle is off. It will export as 12:10:25 AM (HH:MM:SS AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The Nested Value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, choose the Workspace Fields that you want to export by moving them to the Selected Fields box, then click **Continue**. Optionally, you can enter field name aliases to replace the original workspace field names in the exported load file. The Workspace Fields box displays all available fields, but only the fields in the Selected Fields box will be exported.

Note: The Production::Begin Bates and Production::End Bates fields automatically populate in the Selected Fields column.

You can do the following to move fields:


- Highlight a field and click one of the directional arrow buttons in the center to move it between boxes.
- Double-click on a field to move it between boxes.
- Use CTRL+ left mouse click to select multiple fields, then choose the desired directional arrow to move between boxes.

• In Selected Fields column, set the load file column order by dragging the fields to their proper ordering position.



Note: Field aliases should not include delimiters that define the load file structure. The job will not start if a field alias includes such delimiter.

7. On the Image Source dialog, select what images you want to export.



Production Images Type:


- Original Images—select to export only the original, non-produced images.
- **Produced Images**—select to export a produced version of the images.

Select Productions:


- **Include original images** toggle—select to export original images for the documents that are not in a specified production.
- 8. Move the productions that you want to export from the **Available Productions** box to the **Selected Productions** box.

Note: Any produced native files will be exported as a native instead of an image. Only one produced image is exported based on precedence in the list. If the document is in the topmost production, that version is exported. If not, Relativity checks for the document in the second production and so on. If the document is not a part of any of the selected productions, and "Include original images" toggle is enabled, then the original document is produced.

9. On the File Settings dialog, select the options to include native files, images, and/or PDFs in the exported data, then click **Continue**.



- Export Native Files toggle—select this option to export native files.
- Export Images toggle—select this option to include images in the export. If toggled on, then you must set the **Data File Format** for image-level load file, that is Opticon, IPRO, or IPRO (FullText), and the **File Type** for export images, that is Single-page TIFF/JPG, Multi-page TIFF/JPG, or Rendered PDF.
- Export PDF toggle—select this option to include existing stored PDFs in the export. No document-to-PDF conversion functionality is performed in this step. The PDFs must already exist as PDF files. If this option is toggled on, then you must set the **Data File Format** for PDF-level load file, that is Opticon, IPRO, or IPRO (FullText).
- 10. On the File And Folders dialog, choose the desired naming convention and folder structure for the exported files, then click **Continue**.



Text and Native File Names:

- Named after—select one of the following naming conventions for exported files:
 - **Control Number**—select this option to name the files using the document identifier/control number.
 - **Custom name**—select this option to customize the file names. If selected, enter data in the following fields that appear:
 - Prefix—choose whether to have the prefix be the Control Number or Production Begin Bates.
 - Select spacing—select the desired spacing option from the drop-down list.
 - Select field—choose a field from your workspace or choose Custom Text and enter your text.
 - Preview—you will be able to view a Preview of the custom file name to see if it's
 what you want and make changes in the fields as needed.
- **Append original filename** toggle—select this option to append the original file name, which is defined as the file name as it was on disk, to the end of the exported file name.


Folder Structure:

• **Group files by**—select one of the options below for how to group the exported files:


Note: Depending on the structure of your exported data, export job performance degradation may result and be several times longer when using **Workspace Structure** compared with using **File Type**. Unless it is necessary to use Workspace Structure, we recommend using the **File Type** option for the export job.

- Workspace Structure—select this option to preserve the workspace folder structure.

 This option may reduce the time of preparing production data since the files will not need to be manually realigned later to replicate the folder structure in the workspace.
- **File Type**—select this option to group files by their type and place them in separate folders based on type, such as in Natives, Images, Text, and PDFs folders.
- 11. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of the load file.
- **Text File Encoding**—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.




To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.

During an export, the system checks the first field in the list for text. If the field is null, it checks the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

- 12. Click Continue.
- 13. (Optional) In the Advanced Settings dialog, toggle on **Set Custom Information** if you want to customize the volume and folder information. Otherwise, leave the toggle off.




For more information, see <u>Load file export recommendations</u>.

Volume Information —this section controls the naming and size of the volume identifier. Set the following options in this section:

- **Prefix**—enter the alpha prefix for the volume identifier.
- **Start**—enter the first number used for the numeric section of the volume identifier. Multiple volumes increment numbers during export creating unique volume identifiers.
- # of digits—enter the number of digits attached to the prefix. For example, if you enter 3, the output is VOL001, VOL002, and so on.
- Max Size (MB)—enter the maximum size allowed for each volume.

Subdirectory Information—this section controls the naming and size of volume sub-folders. Set the following options in this section:

- Image Prefix—enter the alpha prefix for the sub-directory that stores exported images.
- Native Prefix—enter the alpha prefix for the sub-directory that stores exported native files.
- Text Prefix—enter the alpha prefix for the sub-directory that stores exported extracted text files.
- PDF Prefix—enter the alpha prefix for the sub-directory that stores exported extracted PDF files
- Start—enter the starting number for the sub-directories.
- # of digits—select the number of digits of the sub-directory prefix. For example, if you enter 3, the output is IMG001, IMG002, and so on.
- Max Files—select the number of files to store in each sub-directory.
- 14. Click Continue.
- 15. On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.




16. (Optional) Click Save Settings on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file (.ie file extension) and save it on your computer. This way you can reuse these settings when creating a new export job with Import/Export.

Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other RelativityOne data transfer tools.

- 17. Click the **Export** button to start the exporting process.
- 18. When it's complete, the job summary lists the records exported successfully, including Load files containing .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can track the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running. The transfer job will continue uninterrupted. You can monitor the progress and history of the job within Express Transfer. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

• If using Import/Export in web only mode, the application generates a zip file containing the exported data that can be download. Click the **Download** button to save the exported data zip file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

If you chose to Export to Staging Area when setting up your export job on the Export Settings
dialog, the application automatically exports data to your RelativityOne file share and skips the
downloading process. Go to the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job page and clicking the job name link. The Job page also contains more details about all jobs.

8.3 Exporting a production set load file

You can use Import/Export to export a production set load file out of RelativityOne.


If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.

Refer to Import/Export load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To export a production load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.

3. On the Choose Workflow dialog, click the **Export** button, then click **Production Set**.



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Export Settings dialog, complete the following fields and click Continue.



Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- **Profile**—the job configuration settings that were previously saved to a profile file (.ie or .kw*). They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - **None**—select this option if you do not desire to use a profile for this export or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later on the Export Job Configuration Summary dialog. The file extension for the new profile created will be ".ie".

- From Local Disk Profiles—use this option to select a previously saved Import/Export profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use the drag and drop feature or browse for a file to choose it. All job settings provided within the selected profile file will be automatically entered where applicable in the succeeding workflow dialogs.
- **Production**—choose the desired production set to export.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.


- Staging Area—select this option to create a copy of the data in the StructuredData folder in the Staging Area. You will need to use Staging Explorer later to download data. The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected data in the StructuredData folder in the Staging Area, as well as download it to your local disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths. You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:

- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.



- Data File Format—select one of the formats below for the load file you are exporting:
 - .dat (Concordance)—load file exports with the standard Concordance delimiters.
 - .csv (Comma separated)—load file exports with comma separated delimiters
 - .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
 - .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed.




• **Start Line**—select a line (record number) that identifies the initial document for export. The application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.

- Data File Encoding—select the encoding type for the document-level load file from the dropdown
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to include seconds with the exported date and time information. For example, the time will export as 12:10 AM (HH:MM AM/PM) when the toggle is off. It will export as 12:10:25 AM (HH:MM:SS AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The nested value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, choose the Workspace Fields that you want to export by moving them to the Selected Fields box, then click **Continue**. Optionally, you can enter field name aliases to replace the original workspace field names in the exported load file. The Workspace Fields box displays all available fields, but only the fields in the Selected Fields box will be exported.

Note: The Production::Begin Bates and Production::End Bates fields automatically populate in the Selected Fields column.


You can do the following to move fields:

- Highlight a field and click one of the directional arrow buttons in the center to move it between boxes.
- Double-click on a field to move it between boxes.
- Use CTRL+ left mouse click to select multiple fields, then choose the desired directional arrow to move between boxes.
- In Selected Fields column, set the load file column order by dragging the fields to their proper ordering position.




Note: Field aliases should not include delimiters that define the load file structure. The job will not start if a field alias includes such delimiter.

7. In order to include native files and/or images in the exported data, select the corresponding options on the File Settings dialog, then click **Continue**.



Natives:

- **Export Native Files** toggle—select this option to export native files Production:
 - **Export Images** toggle—select this option to include images in the export. If this option is toggled on, then you must set the Data File Format and the File Type for export images.
 - **Data File Format**—select one of the formats for image-level load file: Opticon, IPRO, or IPRO (FullText).
 - **File Type**—select one of the file types: Single-page TIFF/JPG, Multi-page TIFF/JPG, or Rendered PDF.
- 8. On the File And Folders dialog, choose the desired naming convention and folder structure for the exported files, then click **Continue**.




Text and Native File Names:

- Named after—select one of the following naming conventions for exported files:
 - Control Number—select this option to name the files after the control number.
 - Production Begin Bates—select this option to name the files after the production number.
 - **Custom name**—select this option to customize native and text file names. If this option is selected, enter data in the following fields that are displayed:
 - Prefix—choose whether to have the prefix be the Control Number or Production Begin Bates.
 - Select spacing—select the desired spacing option from the drop-down list.
 - **Select field**—choose a field from your workspace or choose **Custom Text** and provide your text.
 - **Preview**—you will be able to view a Preview of the custom file name to see if it's what you want and make changes in the fields as needed.
- Append original filename toggle—select this option to append the original file name, which is
 defined as the file name as it was on disk, to the end of the exported file name.
 Folder Structure:


• Group files by—select one of the options below for how to group the exported file:

Note: Depending on the structure of your exported data, export job performance degradation may result and be several times longer when using **Workspace Structure** compared with using **File Type**. Unless it is necessary to use Workspace Structure, we recommend using the **File Type** option for the export job.

- **File Type**—select this option to group files by their type and place them in separate folders based on type, such as in Natives, Images, Text, and PDFs folders.
- Workspace Structure—select this option to preserve the workspace folder structure. This option may reduce the time of preparing production data since the files will not need to be manually realigned later to replicate the folder structure in the workspace.
- 9. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of your load file.
- **Text File Encoding**—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.



To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.


During an export, the system checks the first field in the list for text. If the field is null, it checks the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

Note: If you have workflows that rely on clearing a text field for multiple production versions, you will need to ensure that you clear this field using either Mass Replace or a load file that sets the values to NULL. Operations such as Mass Edit will clear the field but set it to blank instead of null. This may result in exporting blank text files.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

10. Click Continue.

(Optional) In the Advanced Settings dialog, toggle on Set Custom Information if you want to customize the volume and folder information using the fields below. Otherwise, leave the toggle off.




For more information, see <u>Load file export recommendations</u>.

Volume Information —this section controls the naming and size of the volume identifier. Set the following options in this section:

- **Prefix**—enter the alpha prefix for the volume identifier.
- **Start**—enter the first number used for the numeric section of the volume identifier. Multiple volumes increment numbers during export creating unique volume identifiers.
- # of digits—enter the number of digits attached to the prefix. For example, if you enter 3, the output is VOL001, VOL002, and so on.
- Max Size (MB)—enter the maximum size allowed for each volume.

Subdirectory Information —this section controls the naming and size of volume sub-folders. Set the following options in this section:

- Image Prefix—enter the alpha prefix for the sub-directory that stores exported images.
- Native Prefix—enter the alpha prefix for the sub-directory that stores exported native files.
- Text Prefix—enter the alpha prefix for the sub-directory that stores exported extracted text files.
- PDF Prefix—enter the alpha prefix for the sub-directory that stores exported extracted PDF files.
- Start—enter the starting number for the sub-directories.
- # of digits—select the number of digits of the sub-directory prefix. For example, if you enter 3, the output is IMG001, IMG002, and so on.
- Max Files—select the number of files to store in each sub-directory.
- 12. Click Continue.
- 13. On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.




14. (Optional) Click Save Settings on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file, .ie file extension. Save it on your computer so you can reuse these settings when creating a new export job with Import/Export.

Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other RelativityOne data transfer tools.

- 15. Click the **Export** button to start the exporting process.
- 16. When it's complete, the job summary lists the records exported successfully, including Load files containing .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can track the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running. The transfer job will continue uninterrupted. You can monitor the progress and history of the job within Express Transfer. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

If using Import/Export in web only mode, the application generates a zip file containing the
exported data that can be download. Click the **Download** button to save the exported data zip
file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

If you chose to Export to Staging Area when setting up your export job on the Export Settings
dialog, the application automatically exports data to your RelativityOne file share and skips the
downloading process. Go the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job Page and clicking the job name link. The Job page also contains more details about all jobs.

8.4 Exporting an RDO load file

You can use Import/Export to export Relativity's dynamic objects (RDO) load file out of RelativityOne.


If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.

Refer to Import/Export load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To export an RDO load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.

3. On the Choose Workflow dialog, click the **Export** button, then click **RDO**.



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Export Settings dialog, complete the following fields, then click **Continue**:



Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- Relativity Object Type—select the Object Type you want to export.

Note: If you need to perform a mass export of native translated files, select Translated Documents as the object type. See Mass exporting translated documents and the Community article Mass Export Native Translated files via Import/Export.

• View—select the View for the selected Object Type.

Note: If exporting translated files, you can use Views if you do not want to export all the translated documents in the workspace. Create a new View on the "Translated Documents Object" and use Conditions to limit it to specific documents. See Mass exporting translated documents and the Community article Mass Export Native Translated files via Import/Export.

- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - **None**—select this option if you do not desire to use a profile for this export or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later on the Export Job Configuration Summary dialog. The file extension for the new profile created will be ".ie".
 - From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use
 the drag and drop feature or browse for a file to choose it. All job settings provided within
 the selected profile file will be automatically entered where applicable in the succeeding
 workflow dialogs.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.


- Staging Area—select this option to create a copy of the data in the StructuredData folder in the Staging Area. You will need to use Staging Explorer later to download data. The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected
 data in the StructuredData folder in the Staging Area, as well as download it to your local
 disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths. You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:

- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.




- Data File Format—select one of the formats below for the load file you are exporting:
 - .dat (Concordance)—load file exports with the standard Concordance delimiters.
 - .csv (Comma separated)—load file exports with comma separated delimiters
 - .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
 - .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed when this option is selected.




- **Start Line**—select a line (record number) that identifies the initial document for export. The application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.
- Data File Encoding—select the encoding type for the document-level load file from the dropdown.
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to
 include seconds with the exported date and time information. For example, the time will export
 as 12:10 AM (HH:MM AM/PM) when the toggle is off. It will export as 12:10:25 AM (HH:MM:SS
 AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The Nested Value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, choose the Workspace Fields that you want to export by moving them to the Selected Fields box, then click **Continue**. Optionally, you can enter field name aliases to replace the original workspace field names in the exported load file. The Selected Fields column is automatically populated with fields that are included in the selected view. The Workspace Fields box displays all available fields. Only the fields listed in the Selected Fields box will be exported. You can do the following to move fields:
 - Highlight a field and click one of the directional arrow buttons in the center to move it between boxes.
 - Double-click on a field to move it between boxes.
 - Use CTRL+ left mouse click to select multiple fields, then choose the desired directional arrow to move between boxes.

• In Selected Fields column, drag fields up and down to set the load file column order.




Note: Field aliases should not include delimiters that define the load file structure. The job will not start if a field alias includes such delimiter.

7. To include native files in the exported data, toggle on **Export Native Files** on the File Settings dialog, and click **Continue**.




8. On the File And Folders dialog, choose the desired naming convention and folder structure for the exported files, then click **Continue**.




Text and Native File Names:

- Named after—select one of the following naming conventions for exported files:
 - Identifier—select this option to name the files using the document identifier/control number.
 - **Custom name**—select this option to customize the file names. If this option is selected, enter data in the following fields that are displayed:
 - Prefix—choose whether to have the prefix be the Control Number or Production Begin Bates.
 - Select spacing—select the desired spacing option from the drop-down list.
 - **Select field**—choose a field from your workspace or choose **Custom Text** and provide your text.
 - **Preview**—you will be able to view a Preview of the custom file name to see if it's what you want and make changes in the fields as needed.
- **Append original filename** toggle—select this option to append the original file name, which is defined as the file name as it was on disk, to the end of the exported file name.
- 9. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of the load file.
- Text File Encoding—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.




To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.

During an export, the system checks the first field in the list for text. If the field is null, it checks the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

10. Click Continue.

11.	(Optional) In the Advanced Settings dialog, toggle on Set Custom Information if you want to customize the volume and folder information. Otherwise, leave the toggle off.




For more information, see <u>Load file export recommendations</u>.

Volume Information —this section controls the naming and size of the volume identifier. Set the following options in this section:

- **Prefix**—enter the alpha prefix for the volume identifier.
- **Start**—enter the first number used for the numeric section of the volume identifier. Multiple volumes increment numbers during export creating unique volume identifiers.
- # of digits—enter the number of digits attached to the prefix. For example, if you enter 3, the output is VOL001, VOL002, and so on.
- Max Size (MB)—enter the maximum size allowed for each volume.

Subdirectory Information —this section controls the naming and size of volume sub-folders. Set the following options in this section:

- Image Prefix—enter the alpha prefix for the sub-directory that stores exported images.
- Native Prefix—enter the alpha prefix for the sub-directory that stores exported native files.
- Text Prefix—enter the alpha prefix for the sub-directory that stores exported extracted text files.
- PDF Prefix—enter the alpha prefix for the sub-directory that stores exported extracted PDF files
- Start—enter the starting number for the sub-directories.
- # of digits—select the number of digits of the sub-directory prefix. For example, if you enter 3, the output is IMG001, IMG002, and so on.
- Max Files—select the number of files to store in each sub-directory.
- 12. Click Continue.
- On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.




14. (Optional) Click Save Settings on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file, .ie file extension. Save it on your computer so you can reuse these settings when creating a new export job with Import/Export.

Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other data transfer tools.

- 15. Click the **Export** button to start the exporting process.
- 16. When it's complete, the job summary lists the records exported successfully, including Load files containing .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can monitor the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running, if desired, and the transfer job will continue uninterrupted. You can monitor the progress and history of the job within Express Transfer. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

If using Import/Export in web only mode, the application generates a zip file containing the
exported data that can be download. Click the **Download** button to save the exported data zip
file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

If you chose to Export to Staging Area when setting up your export job on the Export Settings
dialog, the application automatically exports data to your RelativityOne file share and skips the
downloading process. Go the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job Page and clicking the job name link. The Job page also contains more details about all jobs.

8.5 Exporting a saved search load file

You can use Import/Export to export a saved search load file out of RelativityOne.


If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.

Refer to Import/Export load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To export a saved search load file:


- 1. Use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.

3. On the Choose Workflow dialog, click the **Export** button, then click **Saved Search**.



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Export Settings, complete the following fields, then click **Continue**:



Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - **None**—select this option if you do not desire to use a profile for this export or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later on the Export Job Configuration Summary dialog. The file extension for the new profile created will be ".ie".

- From Local Disk Profiles—use this option to select a previously saved Import/Export profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use the drag and drop feature or browse for a file to choose it. All job settings provided within the selected profile file will be automatically entered where applicable in the succeeding workflow dialogs.
- Saved Search—choose the desired saved search to export.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.


- Staging Area—select this option to create a copy of the data in the StructuredData folder in the Staging Area. You will need to use Staging Explorer later to download data. The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected data in the StructuredData folder in the Staging Area, as well as download it to your local disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths.
 You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:

- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.



- Data File Format—select one of the formats below for the load file you are exporting:
 - .dat (Concordance)—load file exports with the standard Concordance delimiters.
 - .csv (Comma separated)—load file exports with comma separated delimiters.
 - .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
 - .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed when this option is selected.



Start Line—select a line (record number) that identifies the initial document for export. The
application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.


- Data File Encoding—select the encoding type for the document-level load file from the dropdown
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to include seconds with the exported date and time information. For example, the time will export as 12:10 AM (HH:MM AM/PM) when the toggle is off. It will export as 12:10:25 AM (HH:MM:SS AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The Nested Value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, choose the Workspace Fields that you want to export by moving them to the Selected Fields box, then click **Continue**. Optionally, you can enter field name aliases to replace the original workspace field names in the exported load file. The Workspace Fields box displays all available fields, but only the fields in the Selected Fields box will be exported.

Note: The Production::Begin Bates and Production::End Bates fields automatically populate in the Selected Fields column.

You can do the following to move fields:


- Highlight a field and click one of the directional arrow buttons in the center to move it between boxes.
- Double-click on a field to move it between boxes.
- Use CTRL+ left mouse click to select multiple fields, then choose the desired directional arrow to move between boxes.

• In Selected Fields column, set the load file column order by dragging the fields to their proper ordering position.



Note: Field aliases should not include delimiters that define the load file structure. The job will not start if a field alias includes such delimiter.

7. On the Image Source dialog, select what images you want to export.



Production Images Type:


- **Original Images**—select to export only the original, non-produced images.
- **Produced Images**—select to export a produced version of the images.

Select Productions:


- **Include original images** toggle—select to export original images for the documents that are not in a specified production.
- 8. Move the productions that you want to export from the **Available Productions** box to the **Selected Productions** box.

Note: Any produced native files will be exported as a native instead of an image. Only one produced image is exported based on precedence in the list. If the document is in the topmost production, that version is exported. If not, Relativity checks for the document in the second production and so on. If the document is not a part of any of the selected productions, and "Include original images" toggle is enabled, then the original document is produced.

9. On the File Settings dialog, select the options to include native files, images, and/or PDFs in the exported data, then click **Continue**.



- Export Native Files toggle—select this option to export native files.
- Export Images toggle—select this option to include images in the export. If toggled on, then you must set the **Data File Format** for image-level load file, that is Opticon, IPRO, or IPRO (FullText), and the **File Type** for export images, that is Single-page TIFF/JPG, Multi-page TIFF/JPG, or Rendered PDF.
- Export PDF toggle—select this option to include existing stored PDFs in the export. No document-to-PDF conversion functionality is performed in this step. The PDFs must already exist as PDF files. If this option is toggled on, then you must set the Data File Format for PDF-level load file, that is Opticon, IPRO, or IPRO (FullText).
- 10. On the File And Folders dialog, choose the desired naming convention and folder structure for the exported files, then click **Continue**.



Text and Native File Names:

- Named after—select one of the following naming conventions for exported files:
 - Control Number—select this option to name the files using the document identifier/control number.
 - **Custom name**—select this option to customize the file names. If selected, enter data in the following fields that are displayed:
 - Prefix—choose whether to have the prefix be the Control Number or Production Begin Bates.
 - Select spacing—select the desired spacing option from the drop-down list.
 - Select field—choose a field from your workspace or choose Custom Text and enter your text.
 - Preview—you will be able to view a Preview of the custom file name to see if it's
 what you want and make changes in the fields as needed.
- **Append original filename** toggle—select this option to append the original file name, which is defined as the file name as it was on disk, to the end of the exported file name.


Folder Structure:

• Group files by—select one of the options below for how to group the exported files:


Note: Depending on the structure of your exported data, export job performance degradation may result and be several times longer when using **Workspace Structure** compared with using **File Type**. Unless it is necessary to use Workspace Structure, we recommend using the **File Type** option for the export job.

- **File Type**—select this option to group files by their type and place them in separate folders based on type, such as in Natives, Images, Text, and PDFs folders.
- Workspace Structure—select this option to preserve the workspace folder structure.

 This option may reduce the time of preparing production data since the files will not need to be manually realigned later to replicate the folder structure in the workspace.
- 11. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of the load file.
- **Text File Encoding**—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.




To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.

During an export, the system checks the first field in the list for text. If the field is null, it checks the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

- 12. Click Continue.
- 13. (Optional) In the Advanced Settings dialog, toggle on **Set Custom Information** if you want to customize the volume and folder information. Otherwise, leave the toggle off.




For more information, see <u>Load file export recommendations</u>.

Volume Information —this section controls the naming and size of the volume identifier. Set the following options in this section:

- **Prefix**—enter the alpha prefix for the volume identifier.
- **Start**—enter the first number used for the numeric section of the volume identifier. Multiple volumes increment numbers during export creating unique volume identifiers.
- # of digits—enter the number of digits attached to the prefix. For example, if you enter 3, the output is VOL001, VOL002, and so on.
- Max Size (MB)—enter the maximum size allowed for each volume.

Subdirectory Information —this section controls the naming and size of volume sub-folders. Set the following options in this section:

- Image Prefix—enter the alpha prefix for the sub-directory that stores exported images.
- Native Prefix—enter the alpha prefix for the sub-directory that stores exported native files.
- Text Prefix—enter the alpha prefix for the sub-directory that stores exported extracted text files.
- PDF Prefix—enter the alpha prefix for the sub-directory that stores exported extracted PDF files
- Start—enter the starting number for the sub-directories.
- # of digits—select the number of digits of the sub-directory prefix. For example, if you enter 3, the output is IMG001, IMG002, and so on.
- Max Files—select the number of files to store in each sub-directory.
- 14. Click Continue.
- 15. On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.




16. (Optional) Click Save Settings on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file (.ie file extension) and save it on your computer. This way you can reuse these settings when creating a new export job with Import/Export.

Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other RelativityOne data transfer tools.

- 17. Click the **Export** button to start the exporting process.
- 18. When it's complete, the job summary lists the records exported successfully, including Load files containing .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can track the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running. The transfer job will continue uninterrupted. You can monitor the progress and history of the job within Express Transfer. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

If using Import/Export in web only mode, the application generates a zip file containing the
exported data that can be download. Click the **Download** button to save the exported data zip
file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

• If you chose to **Export to Staging Area** when setting up your export job on the Export Settings dialog, the application automatically exports data to your RelativityOne file share and skips the downloading process. Go to the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job Page and clicking the job name link. The Job page also contains more details about all jobs.

8.6 Exporting a saved search or a folder with Access DB load file (MDB)

Note: The import and export workflows with Access DB (MDB) are designed for and are currently available for the Asia-Pacific region. For information on the possibility of enabling this flow in your instance, please contact your Account Representative.

You can use Import/Export to export a saved search or a folder with MDB load file out of RelativityOne.


If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.


Refer to Access DB (MDB) load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.

To export a saved search or a folder load file:

- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.


3. On the Choose Workflow dialog, click the **Export** button, then click **Saved Search** or **Folder**.






Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Export Settings dialog, complete the following fields, then click **Continue**:







Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - None—select this option if you do not desire to use a profile for this export or if you
 intend to create a new profile based on the settings entered in the upcoming steps. You
 will be able to save the profile settings later on the Export Job Configuration Summary
 dialog. The file extension for the new profile created will be ".ie".
 - From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use
 the drag and drop feature or browse for a file to choose it. All job settings provided within
 the selected profile file will be automatically entered where applicable in the succeeding
 workflow dialogs.
- Saved Search—choose the desired saved search to export. This option is available for a saved search export.
- Folders—choose which workspace folder to export. This option is available for a folder export.
- **Export Sub-folders** toggle—select this option to export sub-folders of the previously selected folder. This option is available for a folder export.
- **Views**—select the workspace view that you would like to use to export metadata. This option is available for a folder export.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.

- Staging Area—select this option to create a copy of the data in the StructuredData
 folder in the Staging Area. You will need to use Staging Explorer later to download data.
 The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected
 data in the StructuredData folder in the Staging Area, as well as download it to your local
 disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths. You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:

- (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled.
- 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.

Import/Export Load File Settings < Back Data File Settings Data File Format* • .dat (Concordance) .csv (Comma separated) .html (HTML) .txt (Custom) Start Line* Generate MDB File Data File Encoding* Unicode (UTF-8) Regional Settings (Date And* English (Australia) | en-AU Time) Long time (with seconds)



- .dat (Concordance)—load file exports with the standard Concordance delimiters.
- .csv (Comma separated)—load file exports with comma separated delimiters.
- .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
- .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed when this option is selected.




Export Multiple Choice Fields

as Nested


Continue

Cancel


- Start Line—select a line (record number) that identifies the initial document for export. The
 application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.
- Generate MDB File—toggle on if you want to generate Access DB load file (MDB). This option
 is toggled off by default.
- Data File Encoding—select the encoding type for the document-level load file from the dropdown.
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to export fullname date format with the exported date and time information. For example, when using Regional Setting set to "English (Australia) | en-AU", the date and time will export as 08/04/2025, 9:01 AM (DD/MM/YYYY HH:MM AM/PM) when the toggle is off. It will export as Tuesday, 8 April 2025 09:01:00 AM (Day name, DD Month YYYY hh:mm:ss AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The Nested Value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, configure how to populate individual columns and tables in the exported MDB file. Select options in the three tabs:
 - **Export**—on this tab, map the Relativity workspace fields to the corresponding columns in the Export table.



 Export Extras—on this tab, select which Relativity workspace fields to export into the Export_ extras table. There is also an option to rename a workspace field to a custom name. Label value in MDB file.




Parties—on this tab, select which Relativity workspace fields to export into the Parties table.
 There is also an option to rename a workspace field to a custom name. Correspondence_Type value in MDB file.



Note: For multichoice fields or multiple values separated with a semicolon within a text field, there will be separate row entries created for each such value in the generated record in the Parties table.

7. On the Image Source dialog, select what images you want to export.



Production Images Type:


- Original Images—select to export only the original, non-produced images.
- **Produced Images**—select to export a produced version of the images.

Select Productions:

- **Include original images** toggle—select to export original images for the documents that are not in a specified production.
- 8. Move the productions that you want to export from the **Available Productions** box to the **Selected Productions** box.


Note: Any produced native files will be exported as a native instead of an image. Only one produced image is exported based on precedence in the list. If the document is in the topmost production, that version is exported. If not, Relativity checks for the document in the second production and so on. If the document is not a part of any of the selected productions, and "Include original images" toggle is enabled, then the original document is produced.

9. On the File Settings dialog, select the options to include native files, images, and/or PDFs in the exported data, then click **Continue**.




• Export Native Files toggle—select this option to export native files.

- Export Images toggle—select this option to include images in the export. If toggled on, then
 you must set the Data File Format for image-level load file, that is Opticon, IPRO, or IPRO
 (FullText), and the File Type for export images, that is Single-page TIFF/JPG, Multi-page
 TIFF/JPG, or Rendered PDF.
- Export PDF toggle—select this option to include existing stored PDFs in the export. No document-to-PDF conversion functionality is performed in this step. The PDFs must already exist as PDF files. If this option is toggled on, then you must set the **Data File Format** for PDF-level load file, that is Opticon, IPRO, or IPRO (FullText).
- 10. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of the load file.
- Text File Encoding—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.




To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.

During an export, the system checks the first field in the list for text. If the field is null, it checks the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

11. Click Continue.

12. On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.




13. (Optional) Click **Save Settings** on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file (.ie file extension). Save it on your computer so you can reuse these settings when creating a new export job with Import/Export.

Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other RelativityOne data transfer tools.

- 14. Click the **Export** button to start the exporting process.
- 15. When it's complete, the job summary lists the records exported successfully, including Load files containing .mdb, .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can track the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running. The transfer job will continue uninterrupted. You can monitor the progress and history of the job within <u>Express Transfer</u>. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

• If using Import/Export in web only mode, the application generates a zip file containing the exported data that can be download. Click the **Download** button to save the exported data zip file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

If you chose to Export to Staging Area when setting up your export job on the Export Settings
dialog, the application automatically exports data to your RelativityOne file share and skips the
downloading process. Go to the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job page and clicking the job name link. The Job page also contains more details about all jobs.

8.7 Exporting a production set with Access DB load file (MDB)

Note: The import and export workflows with Access DB (MDB) are designed for and are currently available for the Asia-Pacific region. For information on the possibility of enabling this flow in your instance, please contact your Account Representative.


You can use Import/Export to export a production set with MDB load file out of RelativityOne.

If you want to use Import/Export with Express Transfer, which is the recommended method for data transfer, refer to Express Transfer overview on page 32 for more information. With Express Transfer activated, you can run up to five concurrent export jobs on a single client machine. For more information, see Concurrent and consecutive jobs on page 10.

Refer to Access DB (MDB) load file specifications for more information regarding load files. Also see General recommendations for structured data import and export jobs on page 29.


To export a production load file:

- 1. Use tabs, search, or the quick nav bar to navigate to the **Import/Export Job** page.
- 2. On the Import/Export Job page, click the **New Import/Export Job** button to start a new job.
- 3. On the Choose Workflow dialog, click the Export button, then click Production Set.



Note: If Express Transfer has been activated, the Express Transfer section will display a status of Active. See Activating and deactivating Express Transfer on page 44 for more information.

4. On the Export Settings, complete the following fields and click **Continue**:



Data Source:

- **Job Name**—provide a descriptive job name so that you can quickly identify and track that job on the Import/Export Job page. The Job name field accepts up to 50 characters.
- Folders—choose which workspace folder to export.
- **Export Sub-folders** toggle—select this option to export sub-folders of the previously selected folder.
- Views—select the workspace view that you would like to use to export metadata.

- Profile—the job configuration settings that were previously saved to a profile file (.ie or .kw*).
 They can be reused when creating future jobs with the same or similar settings in RelativityOne. This saves time and effort as well as helps prevent data entry errors when you're mapping fields, for example.
 - **None**—select this option if you do not desire to use a profile for this export or if you intend to create a new profile based on the settings entered in the upcoming steps. You will be able to save the profile settings later on the Export Job Configuration Summary dialog. The file extension for the new profile created will be ".ie".
 - From Local Disk Profiles—use this option to select a previously saved Import/Export
 profile (.ie file) or an existing .kw* profile to reuse the job settings for this workflow. Use
 the drag and drop feature or browse for a file to choose it. All job settings provided within
 the selected profile file will be automatically entered where applicable in the succeeding
 workflow dialogs.

Location and Files:

- Export Location Type—select one or both of these options:
 - Local Disk—select this option to export the selected production set data to the Staging
 Area and compress it to a single zip file. Once complete, you can download the zip file
 with your web browser directly to a local disk by clicking the Download button. This is
 the recommended option when Express Transfer is activated.

Note: This temporary non-Staging Area location is automatically deleted once the download is completed when using Express Transfer or is deleted after 5 days when using web mode for downloads. This data is not included in your Staging Area threshold.


- Staging Area—select this option to create a copy of the data in the StructuredData folder in the Staging Area. You will need to use Staging Explorer later to download data. The exported data will not be compressed.
- Local Disk and Staging Area—select both options to create a copy of the selected data in the StructuredData folder in the Staging Area, as well as download it to your local disk with Express Transfer or web browser.

Notes:

- The StructuredData folder is included in your Staging Area threshold. To avoid additional storage costs, you may want to delete the exported data from that folder once it is no longer needed.
- For some combinations of job configuration and data, Windows system on your local machine may not be able to open ZIP archives due to too long file paths. You may receive an error message: "The compressed (zipped) folder is invalid." For details, go to General recommendations for structured data import and export jobs.

Notifications:


 (Optional) Notification Addresses—enable email notifications by providing the email addresses of those who should get notified once the job completed, failed, or canceled. 5. On the Load File Settings dialog, select the data file format and data file encoding, then click **Continue**.




- Data File Format—select one of the formats below for the load file you are exporting:
 - .dat (Concordance)—load file exports with the standard Concordance delimiters.
 - .csv (Comma separated)—load file exports with comma separated delimiters
 - .html (HTML)—load file is in HTML format and contains hyperlinks to launch any exported files.
 - .txt (Custom)—load file exports with the custom delimiters that you select in the Load File Characters section that is displayed.




- Start Line—select a line (record number) that identifies the initial document for export. The
 application begins by exporting the document with this number and continues by exporting documents with subsequent record numbers.
- Generate MDB File—toggle on if you want to generate Access DB load file (MDB). This option
 is toggled off by default.
- Data File Encoding—select the encoding type for the document-level load file from the dropdown.
- Regional Settings (Date and Time)—select the desired format for the exported date and time data. A preview of the chosen format will appear below the next field. Your selection for this field will remain for future export jobs until you change it or clear the browser cache. Clearing the browser cache will default the format to "English (United States)."
- Long Time (with seconds)—by default, this option is toggled off. Toggle it on if you want to export fullname date format with the exported date and time information. For example, when using Regional Setting set to "English (Australia) | en-AU", the date and time will export as 08/04/2025, 9:01 AM (DD/MM/YYYY HH:MM AM/PM) when the toggle is off. It will export as Tuesday, 8 April 2025 09:01:00 AM (Day name, DD Month YYYY hh:mm:ss AM/PM) when the toggle is on.
- Export Multiple Choice Fields as Nested—select this option to maintain the hierarchy of RelativityOne multiple-choice lists, when applicable. The Nested Value delimiter, a backslash, separates child choices.
- 6. On the Select Fields dialog, configure how to populate individual columns and tables in the exported MDB file. Select options in the three tabs:
 - **Export**—on this tab, map the Relativity workspace fields to the corresponding columns in the Export table.




 Export Extras—on this tab, select which Relativity workspace fields to export into the Export_ extras table. There is also an option to rename a workspace field to a custom name. Label value in MDB file.



Parties—on this tab, select which Relativity workspace fields to export into the Parties table.
 There is also an option to rename a workspace field to a custom name. Correspondence_Type value in MDB file.



7. In order to include native files and/or images and/or PDFs in the exported data, select the corresponding options on the File Settings dialog, then click **Continue**.




Natives:


• **Export Native Files** toggle—select this option to export native files. Native files will be exported if they exist in the production set.

Production:

- Export Images / Export PDFs /Export Images and PDFs toggle—select this option to include additional files in the export. If this option is toggled on, you must set the following options:
 - **Data File Format**—select one of the formats for image/PDF-level load file: Opticon, IPRO, or IPRO (FullText).
 - **File Type**—select one of the file types for images: Single-page TIFF/JPG, Multi-page TIFF/JPG, or Rendered PDF.
- 8. On the Text File Settings dialog, you can select to export text field as files and then choose the text file encoding as follows.



- Export Text Field as Files toggle—determines the export method of the extracted text or OCR. Select this option if you want to export files as individual document-level text files, with one file per document. Deselect it to include text as part of your load file.
- Text File Encoding—if Export Text Field as Files is toggled on, then select the encoding format for the document-level text files.
- Text Fields Precedence—select and assign an order to long text fields that Relativity checks
 for text when performing an export. Relativity adds the Text Fields Precedence column as the
 last column in the load file. You must select at least one long text field to use this functionality.
 Choose the fields from the Add Fields drop-down, then click Add. To delete a selected field,
 click its trashcan icon.



To order the precedence of the fields, click the six-dot handle next to the field name and drag it to the proper ordering position.


During an export, the system checks the first field in the list for text. If the field is null, it checks

the next field in order of precedence for text, and so on. When Relativity finds a field that contains text, it adds the contents of that field to the Text Fields Precedence column in the document load file. Then continues checking the fields for the next document and so on. For example, if you listed the Extracted Text field first and the Production OCR field second, the system would first check the Extracted Text field for content, and if it was null, it would move on to the Production OCR field, and so on.

Note: If you have workflows that rely on clearing a text field for multiple production versions, you will need to ensure that you clear this field using either Mass Replace or a load file that sets the values to NULL. Operations such as Mass Edit will clear the field but set it to blank instead of null. This may result in exporting blank text files.

The Text Fields Precedence column displays the file path to the exported files if you select the **Export Text Field as Files** checkbox above.

- 9. Click Continue.
- On the Export Job Configuration Summary dialog, review the export job settings and go back to make any corrections as needed.



11. (Optional) Click **Save Settings** on the Export Job Configuration Summary dialog to export the job configuration settings entered thus far to its own profile file (.ie file extension). Save it on your computer so you can reuse these settings when creating a new export job with Import/Export.


Note: Import/Export saves job configuration settings to its own profile file format, .ie file extension. Comparing to the legacy .kw* standard, it brings more flexibility as you now can apply saved job settings across various workspaces. The .ie profile file format is not supported in other RelativityOne data transfer tools.

12. Click the **Export** button to start the exporting process.

- 13. When it's complete, the job summary lists the records exported successfully, including Load files containing .mdb, .dat, opt, etc., errors found, and path to your exported files.
 - If using Import/Export with Express Transfer active, the exported files automatically start to download. You can track the download's progress in the Exporting dialog or in Express Transfer. For more information, see Express Transfer Job tracking and history.

Note: If you ran the job with Express Transfer active, you can close the Import/Export application while the job is running. The transfer job will continue uninterrupted. You can monitor the progress and history of the job within <u>Express Transfer</u>. You do not have to be logged into RelativityOne to view information within the Express Transfer application.

If using Import/Export in web only mode, the application generates a zip file containing the
exported data that can be download. Click the **Download** button to save the exported data zip
file to your computer, or click the **Close** button to close the dialog without downloading the file.



Note: When downloading zip files to your computer, you can configure your browser to allow you save the zip file to a custom file name of your choosing as well as to a specific folder destination instead of using the default file name and destination. In the Settings menu of your browser, select Downloads. Toggle on the option to ask where to save or what to do with each file before downloading. Now, when you click the **Download** button in the Exporting dialog, your browser will display a dialog that allows you to change the default zip file name and select a destination other than the default one. If needed, you can also create a new folder in the chosen destination for the exported data.

If you chose to Export to Staging Area when setting up your export job on the Export Settings
dialog, the application automatically exports data to your RelativityOne file share and skips the
downloading process. Go the path listed on the dialog to access the exported data files.

For more information on where Import/Export saves files, see the Community article, Import/Export: Where Files Are Saved By The Import/Export Application.

You can always view the job's Exporting dialog information after it's closed by going to the Import/Export Job Page and clicking the job name link. The Job page also contains more details about all jobs.


9 Import/Export Job tracking and history

The Import/Export Job page enables you to monitor the progress of jobs currently running, review previous jobs that were executed, and view other pertinent job details at the workspace level.

Note: To monitor jobs at the instance level, see Import/Export queue on page 230.

9.1 Reviewing the Import/Export Job page

To access the page, use tabs, search, or the quick nav bar to navigate to the Import/Export Job page.



The following columns are displayed on the Import/Export Job page:

- Name—the name of the job. You can click this link to:
 - Return to the data transfer progress dialog if the job is still in progress.
 - View the data transfer summary if the job has completed.

Note: You may need to refresh the Import/Export Job page to see the job's current progress.

- Job Workflow
 - Unprocessed—for imports of raw native files that require file processing.
 - Document Import—for imports of document load files.
 - Image Import—for imports of image load files.
 - Production Import—for imports of production load files.
 - Production Export—for exports of production load files.
- Job Status—the current job status.

General job statuses:

- **New**—a new job has been configured but has not been started.
- **Uploading phase**—data is being uploaded to RelativityOne. Statuses include: Uploading, Upload Completed, Upload Failed, and Upload Canceled.
- **Extracting phase**—uploaded data is being extracted. Statuses include: Extraction Requested, Extraction Request Failed, Extracting, Extraction Failed, and Extraction Canceled.
- **Transferring phase**—Statuses include: Transfer Requested, Transfer Request Failed, Transferring, Transfer Failed, and Transfer Canceled

 Processing phase (only for unprocessed data import)—Statuses include: Processing Request Failed and Processing Requested.

Detailed job statuses:

- Import job statuses (for structured data import)—Import Job Canceled, Import Job Completed, Import Job Completed with Errors, Import Job Failed, Import Job Inserting, Import Job Scheduled, Import Job Started, and Import Request Failed
- Processing job statuses (for unprocessed data import)—Discovery Not Started, Discovery in Progress, Discovery Completed, Discovery Completed with Errors, Discovery Failed, Discovery Canceled, Publish Not Started, Publish in Progress, Publish Completed, Publish Completed with Errors, Publish Failed, and Publish Canceled.
- Export job statuses—Export Job Started, Export Job Request Failed, Export Job Scheduled, Export Job in Progress, Export Job Completed, Export Job Completed with Errors, Export Job Failed, Export Job Canceled, Download Read, Download Requested, Download in Progress, Download Completed, Download Completed with Errors, Download Failed, and Download Canceled.
- System Created by—the name of the user who started the job.
- Date Started Local—the local date and time when the job started.
- Date End Local—the local date and time when the job was completed.
- **Identifier**—displays the ID of the job.

You can extend the Import/Export Job view by creating your own view. Please refer to Creating a view for more information.

9.2 Support for Mass Operations

The Import/Export Job page only supports the following Mass Operations:

- Delete—select the check box next to the desired Import/Export jobs that you want to delete from the
 Job list. Then, choose Delete from the Mass Operations drop-down list at the bottom of the list. This
 action only removes the job line item from the Job list. It does not remove the job data that was
 already uploaded to or exported from your system. You will need to manually delete those files from
 your system.
- Export to a file—select the check box next to the desired Import/Export jobs in list to export the data in the current view to a text file. Then, choose Export to File from the Mass Operations drop-down list at the bottom of the list. The data currently displayed in the rows and columns of the Job list for the selected jobs will be exported. As you change the columns displayed, so will the data that is exported. If no individual records are selected, Relativity will export all records in the current view, regardless of how many records are displayed per page.


10 Import/Export queue

Import/Export Queue lists the current Import/Export jobs in progress and their status throughout the RelativityOne instance. You can find the Import/Export Queue under the Queue Management tab.

Notes:

- Users who have been granted permissions to the Queue Management tab in the Tab Visibility section of the Admin Security console automatically have access to the Import/Export Queue tab.
- To monitor jobs at the workspace level, see Import/Export Job tracking and history on page 228.

Note: As of February 2025, the new Feature Permissions redefines Relativity's security management by shifting the focus from Object Types and Tab Visibility to feature-based permissions. This new method is simply another option; any feature-specific permissions information already in this topic is still applicable. This new interface enables administrators to manage permissions at the feature level, offering a more intuitive experience. By viewing granular permissions associated with each feature, administrators can ensure comprehensive control, ultimately reducing complexity and minimizing errors. For details see Instance-level permissions and Workspace-level permissions.



The Import/Export Queue provides job information for the following fields:

- **Job Name**—the name of the job, as entered during creation. Click on the link to navigate to the Import/Export job details.
- Job Status—the current state of the job, as represented by the following status values:
 - · Extraction Requested
 - · Extraction In Progress
 - · Extraction Completed
 - Upload Requested
 - · Upload In Progress
 - Upload Retried

- Upload Completed
- · Import Job Requested
- · Import Job Idle
- Import Job Scheduled
- · Import Job Inserting
- · Processing Requested
- Discovery Not Started
- Discovery In Progress
- · Discovery Completed
- Publish Not Started
- Publish In Progress
- Transfer Requested
- Transfer In Progress
- Transfer Completed
- Export Job Requested
- Export Job Scheduled
- Export Job In Progress
- Workspace—the workspace in which the job was created and run.
- Workflow Type—the type of import/export job, as represented by the following values:
 - Unprocessed—job was initiated using the Raw (Unprocessed) Data workflow option within the Import tab.
 - Document Import—job was initiated using the Structured (Processed) Data workflow>Document option within the Import tab.
 - Image Import—job was initiated using the Structured (Processed) Data workflow>Image option within the Import tab.
 - Production Import—job was initiated using the Structured (Processed) Data work-flow>Production option within the Import tab.
 - RDO Import—job was initiated using the Structured (Processed) Data workflow>RDO option within the Import tab.
 - Production Export—job was initiated using the Structured (Processed) Data workflow>Production Set option within the Export tab.
 - Saved Search Export—job was initiated using the Structured (Processed) Data workflow>Saved Search option within the Export tab.
 - Folder Export—job was initiated using the Structured (Processed) Data workflow>Folder option within the Export tab.

- RDO Export—job was initiated using the Structured (Processed) Data workflow>RDO option within the Export tab.
- Start Date—the date on which the job was started.
- Created By—the user who started the job.

Proprietary Rights

This documentation ("**Documentation**") and the software to which it relates ("**Software**") belongs to Relativity ODA LLC and/or Relativity's third party software vendors. Relativity grants written license agreements which contain restrictions. All parties accessing the Documentation or Software must: respect proprietary rights of Relativity and third parties; comply with your organization's license agreement, including but not limited to license restrictions on use, copying, modifications, reverse engineering, and derivative products; and refrain from any misuse or misappropriation of this Documentation or Software in whole or in part. The Software and Documentation is protected by the **Copyright Act of 1976**, as amended, and the Software code is protected by the **Illinois Trade Secrets Act**. Violations can involve substantial civil liabilities, exemplary damages, and criminal penalties, including fines and possible imprisonment.

©2025. Relativity ODA LLC. All rights reserved. Relativity® is a registered trademark of Relativity ODA LLC.